

messages, your applications must specify the `SEND_SMS` uses-permission. To request this permission, add it to the manifest as shown below:

```
<uses-permission android:name="android.permission.SEND_SMS"/>
```

To send a text message, use `sendTextMessage` from the SMS Manager, passing in the address (phone number) of your recipient and the text message you want to send.

```
String sendTo = "5551234";
String myMessage = "Android supports programmatic SMS
messaging!";
SmsManager.sendTextMessage(sendTo, null, myMessage, null, null);
```

The second parameter can be used to specify the SMS service center to use; if you enter null, the default service center will be used for your carrier.

The final two parameters let you specify Intents to track the transmission and successful delivery of your messages.

7.3.3 Tracking and Confirming SMS Message Delivery

To track the transmission and delivery success of your outgoing SMS messages, implement and register Broadcast Receivers that listen for the actions you specify when creating the Pending Intents you pass in to the `sendTextMessage` method.

The first `PendingIntent` parameter, `sentIntent`, is fired when the message either is successfully sent or fails to send. The result code for the Broadcast Receiver that receives this Intent will be one of the following:

- **Activity.RESULT_OK:** To indicate a successful transmission
- **SmsManager.RESULT_ERROR_GENERIC_FAILURE:** To indicate a nonspecific failure
- **SmsManager.RESULT_ERROR_RADIO_OFF:** When the phone radio is turned off
- **SmsManager.RESULT_ERROR_NULL_PDU:** To indicate a PDU (protocol description unit) failure

The second `PendingIntent` parameter, `deliveryIntent`, is fired only after the destination recipient receives your SMS message.

A typical pattern for sending an SMS and monitoring the success of its transmission and delivery looks like this:

```
String SENT_SMS_ACTION = "SENT_SMS_ACTION";
String DELIVERED_SMS_ACTION = "DELIVERED_SMS_ACTION";

// Create the sentintent parameter
```