

```

        new IntentFilter(SENT_SMS_ACTION));

        registerReceiver(new BroadcastReceiver() {
            @Override
            public void onReceive(Context _context,
Intent _intent)

                {
                    [ ... SMS delivered actions ... ]
                }
        },
        new IntentFilter(DELIVERED_SMS_ACTION));

// Send the message
smsManager.sendTextMessage(sendTo, null, myMessage,
sentPI, deliverPI);

```

7.3.4 Conforming to the Maximum SMS Message Size

SMS text messages are normally limited to 160 characters, so longer messages need to be broken into a series of smaller parts. The SMS Manager includes the `divideMessage` method, which accepts a string as an input and breaks it into an `ArrayList` of messages, wherein each is less than the maximum allowable size.

You can then use the `sendMultipartTextMessage` method on the SMS Manager to transmit the array of messages:

```

ArrayList<String>    messageArray    =    smsManager.
divideMessage(myMessage);

    ArrayList<PendingIntent>    sentIntents    =    new
ArrayList<PendingIntent>();

    for (int i = 0; i <messageArray.size(); i++)
        sentIntents.add(sentPI);

smsManager.sendMultipartTextMessage(sendTo,
                                    null,
                                    messageArray,
                                    sentIntents, null);

```

The `sentIntent` and `deliveryIntent` parameters in the `sendMultipartTextMessage` method are `ArrayLists` that can be used to specify different Pending Intents to fire for each message part.