

Flash Builder does not enable you to create a single Flex project whose applications can be deployed on either Flash Player or AIR. Each project must specify one and only one of these deployment options. Flash Builder can share resources between multiple projects so that each project is created as a shell for a particular deployment option, and the bulk of an application's resources are maintained in a third project known as a Flex Library Project, which compiles to a shareable SWC file. In Flash Builder 4.5, you can convert a project that was originally created for the Web to a desktop application that's deployed with Adobe AIR. Right-click on the project in the Project Navigator view and choose **Add. Change Project Type > Convert to Desktop/Adobe AIR Project**. You'll need to make any required code changes to the project, such as changing the root element of the main application file to use the Windowed Application component, but you won't need to recreate the project from scratch.

The Flex SDK version is set to the default SDK (currently "Flex 4.5") or a specific version of the SDK. Flex 4.5 projects use the new Spark components but can also use the older Halo components. They also implement new view state management syntax and other language features of the newer SDK. Flex 3.4 and older projects don't have access to the new Spark components and use the older view state management syntax.

ASP.NET, ColdFusion, J2EE (also known as Java EE or simply JEE) and PHP are the server technologies directly supported by Flash Builder. When you select J2EE as your server technology, you can then select either Adobe LiveCycle Data Services ES or the open-source product BlazeDS. When you select ColdFusion as your server technology, you're also prompted to select LiveCycle Data Services ES, BlazeDS, or ColdFusion Flash Remoting as a communications option. In ColdFusion 9, BlazeDS is installed automatically with the ColdFusion server. See Adobe's ColdFusion support web site at www.adobe.com/support/coldfusion for more information. Flash Builder 4.5 unlike its previous versions enables you to switch to a different application server for an existing project. Choose **Project > Properties > Flex Server**, select an application server, and configure it for use with the current project.

Henceforth we will assume that you've set the application server type to None until and unless specified. The next screen of the Flex Project wizard asks you to provide the Compiled Flex application location, also known as the Output folder. The default is a sub folder of the project root named bin-debug. This folder contains a compiled version of the application,