

```

Item', 'http://www.URLLink1.com', 'http://www.URLLink1.com/
favicon.ico');
    window.external.msSiteModeAddJumpListItem('Twitter',
'http://www.twitter.com/consumermate, 'http://a3.twimg.
com/a/1294164987/images/iefavicon.ico');
    window.external.msSiteModeAddJumpListItem('Internet
Explorer 9', 'http://bit.ly/b9HBZu', 'http://Microsoft.com/
ie/favicon.ico');
    window.external.msSiteModeShowJumplist();
    //window.external.msSiteModeClearJumplist();
}

```

The first if statement checks to see if the current page was launched as a pinned site using the `msIsSiteMode` method. (If the page is just running within the browser and isn't pinned, none of this functionality will be exposed anyway.)

Create advanced Pinned Sites

Implementing Overlay icons

Overlay icons are used to surface notifications or status to the user. While the pinned site is running, it has the ability to display a small icon overlaid on the Taskbar button, to draw the user's attention back to the site or notify the user that some event has happened. The pinned site can display multiple overlay icons to the user, but it can only display one icon at a time.

A great example is Facebook. If you pin `facebook.com`, you will see that when you have new notifications (new friend requests, messages, etc.),



The Facebook pinned site will overlay a red icon with a white asterisk to notify you.

To implement overlay icons in your own pinned sites, you will need to know how to both set and hide overlay icons.



To display an overlay icon to the user on the Taskbar button, you will use the `msSiteModeSetIconOverlay` method. It takes a parameter which is