

a URL pointing to an icon file (*.ico); this is the icon that will be overlaid on the Taskbar button. There is also a second, optional string parameter for a description of the icon overlay, for accessibility purposes.

- `window.external.msSiteModeSetIconOverlay('Images/info.ico');`

To clear an overlay icon from the Taskbar button, you will use the `msSiteModeClearIconOverlay` method.

- `window.external.msSiteModeClearIconOverlay();`

Implementing Flashing taskbar icons

Perhaps you have an instant messaging program which flashes the taskbar button when a new message comes in? Flashing taskbar buttons are used to signal users that their attention or interaction is needed.

Pinned sites can make their taskbar buttons flash as well. To flash the pinned site taskbar button, use the `msSiteModeActivate` method.

- `window.external.msSiteModeActivate();`

This will cause the taskbar button of the pinned site to start flashing. It will flash 20 times, and then the button will stay highlighted until the window comes to the foreground.

When the pinned site window comes to the foreground, the flashing will deactivate automatically.

- Here is a complete sample:

```
<script type="text/javascript">
    // Flashing TaskBar
    setInterval(flashToolBar, 10000);    // calls flash-
ToolBar every 10000 ms
    function flashToolBar() {
        if (window.external.msIsSiteMode()) {
            window.external.msSiteModeActivate();
        }
    }
</script>
```

Implementing Thumbnail toolbar icons

When you hover the mouse over a Taskbar button of a running application or website, a “thumbnail” pops up. This is a little image of the running window.

With pinned sites, you can create thumbnail toolbar buttons, which are small buttons that will display directly under the thumbnail in that popup.