




Hyper-V may be a requirement if you want to develop for Windows Phone

volume on your computer, even the one you boot from.

You can right click on any volume, and select “Turn BitLocker on” to start the process. This will simply require you to enter a password to use with the drive – you will also be asked to save a copy of the recovery

key somewhere safe – and it will begin encrypting your drive.

You can even encrypt the main operating system drive, but this has some special requirements since the drive has to be unlocked before boot. First of all this requires that Windows has a separate boot partition that isn’t encrypted; if you don’t have this already, we can’t help you here although it is possible to create a separate boot partition even if you don’t have one already. The second requirement is that your system include a TPM (Trusted Platform Module). This requirement however, you can get around.

If you try the process described before on your system drive and it works, then great, you have a TPM module and BitLocker will just work. Otherwise you will need to configure your system to use BitLocker with a TPM. Here is how you can do that:

- ▶ With the Windows start screen open type “gpedit.msc” and press enter to launch the Local Group Policy Editor.
- ▶ Browse to Computer Configuration > Administrative Templates > Windows Components > BitLocker Drive Encryption > Operating System Drives
- ▶ In the right pane, double click the setting “Require additional authentication at startup” and select “Enabled”
- ▶ In the options area ensure that the checkbox before “Allow BitLocker without a compatible TPM...” is checked.
- ▶ Click OK.

Now you should be able to start the BitLocker process on your system drive, and will have the option to either enter a password on startup, or insert a USB drive to boot.