



Byjus selling student data

salsken.ai has secured an exposed server that Byjus was using to sell private and sensitive data. <http://dgit.in/jul21-63>



Android apps in Windows 11

Users can now sideload android applications directly into windows 11. <http://dgit.in/jul21-64>

GiB, and the second drive is `/dev/sdb` of size 100 GiB.

Open GParted, and create a partition table of type GPT on both the drives. On one of the drives, add a FAT32 partition of atleast 512 MiB, a FAT32 partition of 4095 MiB, a SWAP partition at least as large as your physical RAM, and make a BTRFS partition in the remaining space. On the second drive, devote the entire space to a single large partition without a filesystem. For this,



The partitioning scheme

use the “cleared” filesystem option in gparted. It will change to “unknown” after successful partitioning. The computer used in this guide has 4 GiB of RAM, so we create a swap partition of 4 GiB.

Install Pop

Open the Pop!_OS installer. It will ask you for your locale settings again. This time, proceed by choosing custom install. On the next screen, choose to mark all the partitions you created appropriately. So, the small FAT32 is the `/efi/boot` partition, the big FAT32 partition is `/recovery`, the SWAP partition is `Swap`, the small BTRFS partition is `/`. For now, we ignore and the big partition. If you have been following this guide exactly, your disk selection screen should look like the following: Click on Erase and Install to begin installation. You can click on the small terminal icon near the progress bar if you want to take a peek under

the hood while the system installs. At the end of the install process, when it asks you to power off or reboot, do not proceed. Instead, simply ignore it for a while. You cannot minimize this, so you may want to go to a different virtual desktop if it helps (**Ctrl+Super+Down**).

BTRFS Configuration

In this step, we will setup two btrfs subvolumes: one to be mounted later as your root partition, and the other to be mounted as your home partition. Mount the root partition (the btrfs partition from your first drive) onto `/mnt`. Then, change your working directory to it, and create a btrfs subvolume. We will name this subvolume as `@`, following the naming convention used by the Ubuntu installer. Then, we move

all the things created by the Pop installer into the new subvolume. After that, we also make a subvolume named `@home`.

```
sudo mount /dev/sda4 /mnt
cd /mnt
sudo btrfs subvolume create @
ls | grep -v @ | sudo xargs
mv -t @
sudo btrfs subvolume create @
home
```

At this point, if you run `ls` in the terminal, you should see only get the following one line output:

```
@ @home
```

If you see something different, an error has been made at some point, and you should start from the top.

Adding Second Device

We will now add the second device to

the mount point. This will present to the OS as one big filesystem with the combined capacity of both the storage devices. We also run `btrfs balance`, which will try to balance the usage across both devices which make up the filesystem. The balance operation might take a while depending on your disk speed.

You can do this operation at any time, even after installing the system and rebooting into it. But the more data you already have, the longer it will take to balance them across devices. You may also remove any device in the pool in the future via `btrfs device remove`, which will take care of reclaiming the data blocks from the device being removed onto the remaining devices.

```
sudo btrfs device add /dev/
sdb1 /mnt
sudo btrfs balance start /mnt
--full-balance
```

System Configuration Files

We have now significantly changed the state of the system from what the installer did. So, we need to tweak some configuration files to account for our changes. We need to change 4 files in particular, two of which reside on the ESP. The files are `/mnt/@/etc/kernelstub/configuration`, `/mnt/@/etc/fstab`, `/mnt/@/boot/efi/loader/loader.conf`, and `/mnt/@/efi/loader/entries/Pop_OS-current.conf`.

We will change `fstab`, and `loader.conf` by hand, and use the `kernelstub` management utility to change the rest.

We will chroot into the newly installed OS. For this, we bind mount the required paths into `/mnt`.

```
cd /
sudo umount /mnt
sudo mount -o
defaults,subvol=@,ssd,
discard,noatime,space_cache,
compress=zstd,commit=120 /
```