




Figure 1: Htop output




Figure 2: Htop meters




Figure 3: Htop display options

system, with information about how much CPU and memory each process is using as well as the command used to start the process. The information for each process is divided into various columns. Here is what each column means.

PID: Process ID of a process

USER: User owning the process

PR: Priority of the process

NI: The nice value for a process

VIRT: Virtual memory consumption

RES: Physical RAM consumption in kilobytes

SHR: Shared memory consumption

S: Process status (S-sleeping, R-running, etc)

CPU%: CPU consumption

MEM%: Physical RAM consumption

TIME+: Processor time used by the process

COMMAND: Command that started the process

The footer displays the menu options.

Configuring Htop output

Meters: Htop displays only three bars in the header, but more can be added to and removed from it. To add or remove, press F2 -> Select -> Meters under Setup.

The 'Set up' column shows the available settings, the column titled 'left column' shows the list of columns displayed on the left side in the header section in the form of bars, whereas the column titled 'right column' shows the list of columns displayed on the right side in the header section in the form of text.

'Available meters' shows the meters available that can be displayed in the header section.

To add meters, navigate to the appropriate column. Using arrow keys, select the meter you want to add and press F5 to add to the right and F6 to add to the left. Similarly, to delete a meter, navigate to the appropriate meter and press F9.

Display options: To customise display options, select 'Display options' under 'Set up'. Then select or deselect the option you want, and press F10 to save.

Colours: This option helps us choose different colours.

Columns: We can configure the columns displayed for processes and threads in the body section that we saw earlier. Press F2 -> Setup -> Columns. All the currently displayed