

If you try logging in with the newly created credentials, you might encounter the following error displayed on the Nagios Core Web console: 'Unable to get process status' (Figure 2).

This error is displayed as SELinux is enabled on the system. It can be verified as shown below:

```
$ getenforce
Enforcing
```

In order to disable SELinux, you can execute the following command, verify the status again and restart the Nagios service:

```
$ setenforce 0
$ getenforce
Permissive
$ service nagios restart
```

And the outcome is shown in Figure 3.

Again, you can verify the Nagios configuration file for its correctness using the following command:

```
/usr/local/nagios/bin/nagios -v /usr/local/
nagios/etc/nagios.cfg
```

Nagios Core configuration

We have now installed Nagios Core and we can access it from a Web console. On the left pane, a link named 'Hosts' can be observed, which when clicked on displays the list of hosts currently being monitored (Figure 4).

Clearly, we have not added any hosts to Nagios, so it will just show 'localhost' in the list of hosts being monitored.

The same can be observed in the 'Host Status Details' shown in Figure 5. It gives us a brief How To of all the hosts configured to monitoring Nagios and their statuses – the total number of hosts, the number of hosts that are up/down/unreachable, etc.

NRPE installation on a Nagios client: In order to monitor any Linux hosts using Nagios, we need to install the NRPE (Nagios Remote Plugin Executor) client on the host, so that the Nagios server can execute Nagios plugins remotely to

fetch the host/service information.

To proceed with the NRPE installation, we need to download the NRPE tarball from the sources, as follows:

```
$ wget http://liquidtelecom.dl.sourceforge.net/project/
nagios/nrpe-2.x/nrpe-2.15/nrpe-2.15.tar.gz
```

In the next step, we have to extract the tarball, compile the binaries and install them. Prior to that, make sure that 'xinetd' is installed in the system; otherwise, install it manually using Yum.

```
$ yum install xinetd
$ tar -xvzf nrpe-2.15.tar.gz
$ cd nrpe-2.15
$ ./configure
$ make all
$ make install-plugin
$ make install-daemon
$ make install-daemon-config
$ make install-xinetd
```

In the next step, we need to open port 5666 for the NRPE service.

```
$ echo "nrpe 5666/tcp # NRPE" >> /etc/services
```

In the last step, we need to allow requests from the Nagios server. For this, edit the `/etc/xinetd.d/nrpe` file and mention the IP address of the Nagios server in front of 'only_from' as follows:

```
only_from = 127.0.0.1, <NAGIOS-SERVER-IP-ADDRESS>
```

For the changes to take effect, restart the `xinetd` service as follows:

```
$ service xinetd restart
```

To verify the installation of NRPE on the Nagios client, execute the following command from the Nagios server:




Figure 3: Nagios daemon running




Figure 4: Nagios hosts



Figure 5: Nagios host status details