



Figure 5: Redshift status icon in the taskbar



Figure 6: dnf install

```
wget -c https://github.com/jonls/redshift/releases/
download/v1.10/redshift-1.10.tar.xz
```

```
tar xf redshift-1.10.tar.xz
```

```
cd redshift-1.10/
```

```
./configure --prefix=$HOME/redshift/root \
--with-systemduserunitdir=$HOME/.config/systemd/user
```

```
make
```

```
make install
```



**Note:** Earlier, version 1.8 *redshift-gtk* was known as *gtk-redshift* so you might need to change the name while installing. Also, there is *redshift-qt* for the KDE desktop.

## Configuring Redshift

By default, Redshift configures itself based on the user's location. The location is obtained using GeoClue which may or may not work out-of-the-box, in all cases. It can be configured manually. Uninstall the *Redshift-gtk* and **not** Redshift, and follow the steps below to use Redshift without the GUI.

**Location:** The location for Redshift can be set manually by using the *-(location)* flag:

```
redshift -l 22.5:88.3
```

The above is the latitude and longitude of Kolkata, which works for most of India. Feel free to change the above value to that of the city which is nearest to you.

**Temperature:** The temperature of the screen can be set by using the *-(temperature)* flag:

```
redshift -t 4500:3000
```

...where 4500 is the daytime temperature and 3000 is the night temperature.

**Brightness:** The brightness of the screen can be set by using the *-b (brightness)* flag. And the value for it can be between 0.1 and 1.0.

```
redshift -b 0.8
```



**Note:** As I have mentioned above, brightness doesn't reduce the light from the screen but it applies a grey filter, which creates a similar effect. And you can combine the above commands according to your needs.

**Configuration file:** You can also use a configuration file instead of the above commands. Here is the configuration file example given by Jon Lund Steffensen in the Redshift website. You can create the new file in your favourite editor and put it at *~/.config/redshift.conf*:

```
; Global settings for redshift
```

```
[redshift]
```

```
; Set the day and night screen temperatures
```

```
temp-day=5700
```

```
temp-night=3500
```

```
; Enable/Disable a smooth transition between day and night
; 0 will cause a direct change from day to night screen
temperature.
```

```
; 1 will gradually increase or decrease the screen
temperature.
transition=1
```

```
; Set the screen brightness. Default is 1.0.
```

```
;brightness=0.9
```

```
; It is also possible to use different settings for day and
night
```

```
; since version 1.8.
```

```
;brightness-day=0.7
```

```
;brightness-night=0.4
```

```
; Set the screen gamma (for all colors, or each color channel
; individually)
```

```
gamma=0.8
```

```
;gamma=0.8:0.7:0.8
```

```
; This can also be set individually for day and night since
; version 1.10.
```

```
;gamma-day=0.8:0.7:0.8
```

```
;gamma-night=0.6
```

```
; Set the location-provider: 'geoclue', 'geoclue2', 'manual'
```