

First check out the code from the Cockpit repository, as follows:

```
$ git clone https://github.com/cockpit-project/cockpit.git
```

Then, install the dependencies required for Cockpit, as shown below:

```
$ cd cockpit
$ sudo yum-builddep tools/cockpit.spec
$ sudo yum install nodejs npm
$ sudo yum install trickle nbd-server
python-libguestfs qemu \
mock qemu-kvm python curl libvirt-
client libvirt-d qemu-nbd \
krb5-workstation krb5-server
$ npm install phantomjs
```

For building and installing Cockpit, use the following code inside the Cockpit directory:

```

$ cd ~/cockpit
$ mkdir build
$ cd build
$ ../autogen.sh - -prefix=/usr -
-enable-maintainer-mode - -enable-debug
$ make
$ sudo make install
$ sudo cp ../src/bridge/cockpit.pam.
insecure /etc/pam.d/cockpit
$ sudo sh -c "cat ../src/bridge/ssh-d-
reauthorize.pam >> /etc/pam.d/ssh"

```

This will install Cockpit and its support files with the required components.

Running Cockpit

Cockpit can be started using *systemd* commands, as follows:

```
$ systemctl start cockpit.socket
```

Cockpit can be also started as a daemon, using the command below:

```
$ /usr/libexec/cockpit-ws
```

Go to the Web browser and type the following:

https://<YOUR_IP_ADDRESS>:9090




Figure 1: Login screen



Figure 2: Dashboard




Figure 3: Server monitoring




Figure 4: System services

Cockpit can be stopped using the `systemd` command, as follows:

```
$ systemctl stop cockpit.socket cockpit
```

Working with Cockpit

On pointing your Web browser to `https://<COCKPIT_IP>:9090`, you can follow the login prompt (Figure 1).