




Figure 3: Overview of CPU, slices and memory

In addition, you need to create an account at hub.docker.com so that you can work with the cAdvisor image. Just visit the website <https://hub.docker.com/> and sign up with your username, password and email address. Please make sure that you have verified your email address.

Once you have done this, from a terminal, attempt to issue the following command and fill in the details, as follows:

```
$ docker login
username:
password:
email:
```

Should you subsequently see an error like this: `/var/run/docker.sock: permission denied`, then the permissions need to be fixed. What needs to be done for this is shown below:

```
$ ls -l /var/run/docker*
-rw-r--r--
1 root root 4 Apr 9 11:17 /var/run/docker.pid
srw-rw---- 1 root docker 0 Apr 9 11:17 /var/run/docker.sock=
```

We need to replace 'root' by your login name on the machine (for example, Saifi, in this case) for the `docker.sock`

```
$ sudo chown saifi:docker /var/run/docker.sock
root's password:
```

```
$ ls -l /var/run/docker*
-rw-r--r-- 1 root root 4 Apr 9 11:17 /var/run/docker.pid
srw-rw---- 1 saifi docker 0 Apr 9 11:17 /var/run/docker.sock=
```




Figure 4: Per core utilisation




Figure 5: Memory, filesystem utilisation

Now, the login should go through.

Next, pull in the cAdvisor image from the Docker hub. We are using the compiled cAdvisor image that is hosted in a repository at <https://registry.hub.docker.com/u/saifkhan/cadvisor/>

```
$ docker pull saifkhan/cadvisor
```

You will see an output like what's shown below:

Pulling repository saifkhan/cadvisor