

[illegible]

Figure 1: Adding title and metadata

```

<body>
<div class="layout">
  <div id="controls"><!-- DO NOT EDIT --></div>
  <div id="currentitem"><!-- DO NOT EDIT --></div>
  <div id="header"></div>
  <div id="footer"></div>
  <div id="location/date of presentation"></div>
  <div id="slide show title here"></div>
</div>

```

Figure 2: The title slide

that. I will demonstrate how you can easily create simple presentations; once you can do that, complex presentations and creating your own themes will be much easier.

To get started, obtain the vanilla copy of the S5 presentation system—you can download version 1.1, the latest, from <http://meyerweb.com/eric/tools/s5/v1.1/s5-11.zip> or <http://bit.ly/1arWCY>. Decompress it into your working folder, but do NOT change the default directory structure or any file names. The file `s5-blank.html` is the main index file, which we will soon be editing. The `ui` directory contains the CSS and Javascript code that makes S5 work. We will deal with CSS later.

To create a simple presentation using the default theme, edit `s5-blank.html`. Enter the name of the presentation in the head section of this file. Also change the meta tags to the correct date, author and company (see Figure 1 for an example). Don't change anything else in the head section for now.

Moving along to the body section of the document, you will see the layout division. Here you can enter the header and footer that will appear on every slide. S5 requires the division's controls and currentSlide to remain empty to properly render slides; so leave them as they are.

It's now time to create your first slide—the title slide. The first slide in the division, named presentation, is the title slide, as indicated by the place-holder text. Replace the place-holders with your own details.

The next slide division is a template for the rest of your slides—copy and paste it, then edit it so that it contains the text for the new slide. The default layout generates a list of points, as shown in Figure 3.

To create a different structure for your slide, use different HTML elements. The handout division contained in each slide is for text that you wish to appear in printed copies of the slides, but not on screen during the presentation.

Pretty easy, right? To add more slides, just keep on

[illegible]

Figure 3: Defining slides in the presentation

[illegible]

Figure 4: S5-Reloaded additional feature configuration

copying and pasting the slide with place-holders. S5 does not have any limit on the number of slides in a presentation, so you can add as many as you want.

Advanced configuration

The latest version of S5 contains a lot of good additions. The most anticipated feature was dynamic scaling of the font size, based on the window resolution. Initially, you had to hand-edit CSS depending on the window size, and/or manually split one slide into multiple chunks. Now S5 takes care of font scaling.

One feature still lacking in S5 is the ability to scale images in a similar way. However, with S5-Reloaded (more on that later), automatic scaling of images is also possible. Adding images to slides is just like adding images to HTML pages—you add an `img` element. The `height` attribute of the element makes sure that the image is scaled to match the screen resolution.

```
<div class="slide">
<h1>Slide Heading</h1>
<p style="text-align: center;">

</p>
</div>
```

Another of SS's features is the incremental display of content—points are displayed one after the other, in response to a mouse click or pressing a button. To add incremental display for a list of points, just add the class `incremental` to the opening tag for the list, as follows:

```
<ul class="incremental">
<li>point1</li>
<li>point2</li>
</ul>
```