

```
msf > show
Encoders
=====
Name Description
-----
cmd/generic_sh Generic Shell Variable Substitution Command Encoder
generic/nop The "nop" Encoder
mipsbe/longxor XOR Encoder
...snip...
```

There are a number of *show* commands you can use, but the ones you will use most frequently are *show auxiliary*, *show exploits*, and *show payloads*.

search

Msfconsole includes an extensive regular-expression-based *search* functionality. If you have a general idea of what you are looking for, you can use the *search* command. In the output below, a search is being made for MS Bulletin MS09-011. The search function will locate this string within the module references. Note that the naming convention for Metasploit modules uses 'underscores' rather than 'hyphens'.

```
msf > search ms09-001
[*] Searching loaded modules for pattern 'ms09-001'...
Auxiliary
=====
Name Description
-----
dos/windows/smb/ms09_001_write Microsoft SRV.SYS WriteAndX
```

use

When you have decided to use a particular module, issue the *use* command to select it. The *RPORT* (remote port) variable is used as a global variable when running Windows SMB exploits. It is mentioned in the output, set to the preconfigured value of 445, because this port number is used by the Windows SMB service.

```
msf > use dos/windows/smb/ms09_001_write
msf auxiliary(ms09_001_write) > show options
Module options:
Name Current Setting Required Description
-----
RHOST yes The target address
RPORT 445 yes Set the SMB service port
msf auxiliary(ms09_001_write) >
```

connect

By issuing the *connect* command with an IP address and port number, you can connect to a remote host from within *msfconsole* just like you would with *netcat* or *telnet*:

```
msf > connect 192.168.1.1 23
```




Figure 1: MSF Console



Figure 2: MSF Web interface

setg/unsetg

To save time, you can use *setg* to set global variables in *msfconsole* if you plan to use the same values for those variables in multiple exploits and auxiliary modules during a penetration testing session. You can also save these variables for use in your next *msfconsole* session. However, you need to remember that you have saved global variables, or you should make it a habit to always check your options before you 'run' or 'exploit'. You can use the *unsetg* command to unset a global variable. In the examples that follow, variables are entered in 'all-caps' (like '*LHOST*'), but Metasploit is case-insensitive, so it is not necessary to do so.

```
msf > setg LHOST 192.168.1.101
LHOST => 192.168.1.101
msf > setg RHOSTS 192.168.1.0/24
RHOSTS => 192.168.1.0/24
msf > setg RHOST 192.168.1.136
RHOST => 192.168.1.136
msf > save
Saved configuration to: /root/.msf3/config
```

set

The *set* command is used in the same way as *setg*, but the variable's scope is only that of the current module with which you are working.