

Managing Your IT Infrastructure Effectively with Zentyal

Zentyal (formerly eBox Platform) is a program for servers used by small and medium businesses (SMBs). It plays multiple roles—as a gateway, network infrastructure manager, unified threat manager, office server, unified communications server or a combination of all of the above. This is the third and last article in our series on Zentyal.



In previous articles in this series, we discussed various scenarios that included DHCP, DNS and setting up a captive portal. In this article, let's discuss the HTTP proxy, traffic shaping and setting up of 'Users and Computers' modules.

The HTTP proxy set-up

We will start with the set-up of the HTTP proxy module of Zentyal. This module will be used to filter out unwanted traffic from our network. The steps for the configuration are as follows:

1. Open the Zentyal dashboard by using the domain name set up in the previous article or use the IP address.
2. The URL will be <https://domain-name>.
3. Enter the user ID and password.
4. From the dashboard, select **HTTP Proxy** under the **Gateway** section. This will show different options like *General settings*, *Access rules*, *Filter profiles*, *Categorized Lists* and *Bandwidth throttling*.
5. Select *General settings* to configure some basic parameters.
6. Under *General settings*, select *Transparent Proxy*. This option is used to manage proxy settings without making clients aware about the proxy server.
7. Check *Ad Blocking*, which will block all the advertisements from the HTTP traffic.
8. *Cache size* defines the stored HTTP traffic storage area. Mention the size in MBs.
9. Click *Change* and then click *Save changes*.
10. To filter the unwanted sites from the network, block