




Figure 1: Setting up Zentyal for testing purposes




Figure 2: Dashboard used to control the server

- Gateway and UTM, which has configurable network interfaces, high availability, advanced routing, an advanced firewall, traffic shaping and QOS, an advanced HTTP proxy server, a captive portal, a RADIUS server, VPN, an intrusion prevention system and mail filter.

Zentyal modules are customisable and can be handpicked at the time of installation. These features allow users to control most infrastructure management needs efficiently.

In this article, I will cover the setting up of Zentyal Server 3.4. We will explore two different scenarios—first a live scenario and then a test one. Those who do not have a spare server to use, can test run it on VirtualBox, which will be explained later.

Scenario 1: Setting up Zentyal on a production server

Hardware requirements:

- 32/64-bit hardware
- Two network interface cards
- 20 GB of hard disk space

Software requirements:

- Zentyal 3.4 32/64-bit server.

A server has two interface cards: eth0 and eth1. The interface eth0 is connected to the ISP, with a static address, and eth1 is connected to the LAN. The LAN interface is used to supply IP addresses to clients using a DHCP server. Interface eth1 is assigned two local IPs—72.22.22.1 and 172.22.23.1 in order to serve two VLANs (virtual LANs). Each IP address range has some IPs reserved for internal use, which can be assigned for internal servers, copiers, printers, etc, and the rest of the range can be assigned to clients. This range of IP addresses can serve up to 490 clients.

To provide IP addresses automatically to the clients in the network, we use a DHCP server. We also use a local domain so as to provide names to our devices. Names are easier to remember than IP addresses. So, if you want to access any device from the network, just use device name rather than IP address. We have set IAMT as our local domain name. We also use a captive portal, which will authenticate a user on the domain. This portal is also used to provide a download quota for each individual user. This quota is used as a limit for Internet bandwidth usage.

Scenario 2: Setting up Zentyal for testing purposes

Hardware requirements:

A 32/64-bit laptop/desktop, two virtual network interface cards, and 20 GB of hard disk space.

Software requirements:

Zentyal 3.4 32/64-bit server

Those who want to test this server on their local machines can use VirtualBox1 for testing purposes.

For VirtualBox, the Internet is shared with the host operating system; therefore, the primary virtual interface (eth0) of the guest Zentyal server operating system has to be set as DHCP and not static.