

```
service dict {
    unix_listener dict {
        mode = 0660
        user = vmail
        group = vmail
    }
}
```

Let Dovecot listen on Port 143 for *cleartext* connections. There's no point in encrypting for clients connecting from the same machine (the Web mail client, i.e., Roundcube). You can block the *plaintext* Port 143 using *iptables* so that nobody from the Internet connects via the *cleartext* protocol.

The service *LMTP* and *service auth* are interesting parts in the above configuration. In the *LMTP* section, Dovecot is configured to listen for *LMTP* connections at a UNIX socket path. We'll use the same path in Postfix configuration — it tells Postfix where to deliver the mails via *LMTP*.

Postfix is the *SMTP* server, but we need user authentication. Postfix must be configured to use Dovecot's authentication mechanism because we are storing encrypted passwords in the database. Postfix supports Dovecot-SASL. For the same reason, we have configured the Dovecot *service auth* to listen on a UNIX socket for connections.

In *15-lda.conf*, we need the following settings:

```
recipient_delimiter = +
lda_mailbox_autocreate = yes
lda_mailbox_autosubscribe = yes

protocol lda {
    mail_plugins = $mail_plugins sieve
}
```

In the first article in this series, we had created a function *sender_bcc_map* which outputs *username+Sent@domain* for *input username@domain*. In the above configuration, the *recipient_delimiter* option specifies that the email address should be split by +, and the part after + should be treated as the destination folder name. This is something similar to Gmail wherein we can use any number of email aliases, but everything gets delivered to the inbox and filters need to be set up manually. Our mail server does the filtering automatically.

The Sieve plugin is loaded for the *LDA* protocol — it cannot operate on other protocols. Sieve is the RFC defined standard language for mail filtering.

In *20-imap.conf*, we need to load the anti-spam plugin, as follows:

```
protocol imap {
    mail_plugins = $mail_plugins antispam
}
```

Similarly, in *20-lmtp.conf*, load the Sieve plugin for the

LMTP protocol.

The ManageSieve protocol configuration titled *20-managesieve.conf* is as follows:

```
protocols = $protocols sieve

service managesieve-login {
    inet_listener sieves {
        port = 4190
        ssl = yes
    }

    inet_listener sieve {
        port = 4191
        ssl = no
    }
    service_count = 0
    vsz_limit = 256M
}
```

This instructs Dovecot to enable the ManageSieve protocol, with which users configure Sieve filter scripts by themselves. This is required if you want the user to be able to configure filters using Roundcube or other Web mail clients and/or desktop clients like Thunderbird. Since security is important, we'll use two ports for Sieve. The new standard for Sieve says that it is on Port 4191, so it should be open to the public and have SSL. The other port, 4191, will be used for local Web mail client connections.

Coming to the plugin settings in *90-plugin.conf*, we need to configure four plugins — *Fulltext Lucene Search*, *Trash*, *Expire* and *Antispam*:

```
plugin {
    fts = lucene
    fts_lucene = whitespace_chars=@.
    trash = /etc/dovecot/dovecot-trash.conf.ext
    expire = Trash
    expire2 = Trash/*
    expire3 = Junk
    expire4 = Junk/*
    expire_dict = proxy::expire

    antispam_backend = spool2dir
    antispam_allow_append_to_spam = yes
    antispam_spam = Junk
    antispam_trash = Trash
    antispam_spool2dir_spam = /var/lib/dovecot/antispam/spam/%u
    antispam_spool2dir_notspam = /var/lib/dovecot/antispam/ham/%u
}
```

The *trash* plugin is useful when quotas are enabled — it will automatically delete messages from folders when a new