

Now, download the `epel-release-6-8.noarch.rpm` package and install it.

Important notes on EPEL

1. EPEL stands for Extra Packages for Enterprise Linux.
2. EPEL is not a part of RHEL but provides a lot of open source packages for major Linux distributions.
3. EPEL packages are maintained by the Fedora team and are fully open source, with no core duplicate packages and no compatibility issues. They are to be installed using the YUM utility.

The link to download the EPEL release for RHEL 6 (32-bit) is: <http://download.fedoraproject.org/pub/epel/6/i386/epel-release-6-8.noarch.rpm>

And for 64 bit, it is:

http://download.fedoraproject.org/pub/epel/6/x86_64/epel-release-6-8.noarch.rpm

Here, `epel-release-6-8.noarch.rpm` is kept at `/opt`:

Go to the `/opt` directory and change the permission of the files:

```
[root@poundgateway opt]# chmod -R 755 epel-release-6-8.noarch.rpm
[root@poundgateway opt]#
```

Now, install `epel-release-6-8.noarch.rpm`:

```
[root@poundgateway opt]# rpm -ivh --aid --force epel-release-6-8.noarch.rpm
warning: epel-release-6-8.noarch.rpm: Header V3 RSA/SHA256
Signature, key ID 0608b895: NOKEY
Preparing... #####
##### [100%]
1:epel-release #####
##### [100%]
[root@poundgateway opt]#
```

`epel-release-6-8.noarch.rpm` installs the repo files necessary to download the Pound package:

```
[root@poundgateway ~]# cd /etc/yum.repos.d/
[root@poundgateway yum.repos.d]# ll
total 16
-rw-r--r-- 1 root root 957 Nov 4 2012 epel.repo
-rw-r--r-- 1 root root 1056 Nov 4 2012 epel-testing.repo
-rw-r--r-- 1 root root 67 Jul 27 13:30 redhat.repo
-rw-r--r-- 1 root root 529 Apr 27 2011 rhel-source.repo
[root@poundgateway yum.repos.d]#
```

As observed, `epel.repo` and `epel-testing.repo` are the new

added repo files. No changes are made in `epel.repo` and `epel-testing.repo`. Move the default `redhat.repo` and `rhel-source.repo` to the backup location. Now, connect the server to the Internet and, using the `yum` utility, install Pound:

```
[root@PoundGateway ~]# yum install Pound
```

This will install `Pound`, `Pound-debuginfo` and will also install required dependencies along with it.

To verify Pound's installation, type:

```
[root@PoundGateway ~]# rpm -qa Pound
Pound-2.6-2.el6.i686
[root@PoundGateway ~]#
```

The location of the Pound configuration file is `/etc/pound.cfg`

You can view the default Pound configuration file by using the command given below:

```
[root@PoundGateway ~]# cat /etc/pound.cfg
```

Make the changes to the Pound configuration file as shown in the code snippet given below:

- We will comment the section related to "ListenHTTPS" as we do not need HTTPS for now.
 - Add the IP address `192.168.10.30` under the 'ListenHTTP' section.
 - Add the IP address `192.168.10.31` and `192.168.10.32` with Port 80 under 'Service Backend Section', where `[192.168.10.30]` is for the Pound server; `[192.168.10.31]` for Web Server1 and `[192.168.10.32]` for Web Server2.
- The edited Pound configuration file is:

```
[root@PoundGateway ~]# cat /etc/pound.cfg
#
# Default pound.cfg
#
# Pound listens on port 80 for HTTP and port 443 for HTTPS
# and distributes requests to 2 backends running on localhost.
# see pound(8) for configuration directives.
# You can enable/disable backends with poundctl(8).
#
User "pound"
Group "pound"
Control "/var/lib/pound/pound.cfg"

ListenHTTP
Address 192.168.10.30
Port 80
End
```