



TIPS & TRICKS



Making Mozilla Firefox faster

We all know Firefox is a memory hogger. To speed up Firefox, however, you can follow the steps shown below:

1. Open Firefox and in the address bar, type in 'about:config'.
2. Click on the button: 'I'll be careful, I promise'.
3. Use the search bar located on the page to look for 'network.http.pipelining' and double click on it to set its value to 'True'.
4. Create a new Boolean value named 'network.http.pipelining.firstrequest' and set that to 'True', as well.
5. Find 'network.http.pipelining.maxrequests' and double click on it. Then change its value to '8'.
6. Look for 'network.http.proxy.pipelining' and set it to 'True'.
7. Create two new integers named 'nglayout.initialpaint.delay' and 'content.notify.interval'; set them to '0'.
8. Now, restart your browser to experience the difference.

—Vinayak Kulkarni, kulkarnivd2009@gmail.com



Convert ext3 to ext4 file system support

These days, we are getting ext4 file system support in almost every new release of a distribution. However, if you are working on an old flavour that has support for the ext3 file system, you can convert it to ext4 file system support by following a few simple steps, as shown below:

1. Install any latest version of the kernel so that the ext4 patch can be applied to it.
2. Then convert '/dev/sdb1' to ext4 and run the following commands:

```
# cd /; umount /dev/sdb1

# tune2fs -O extents,uninit_bg,dir_index /dev/sdb1

3. Next run fsck

# fsck -pf /dev/sdb1
```

4. Now, simply mount the partition that you have converted.

```
# mount -t ext4 /dev/sdb1 /
```

The following steps are for converting '/boot' to 'ext4':

1. First convert the '/boot' file system as the ext4 file system using the commands above and then open the Grub file and add 'rootfstype=ext4' as the kernel parameter. It will look like what is shown below:

```
title Ubuntu 8.10, kernel 2.6.28.1-vmware-guest-server

root (hd0,1)

kernel /boot/vmlinuz-2.6.28.1-vmware-guest-server
root=UUID=8c2da865-13f4-47a2-9c92-2f31738469e8 ro quiet splash
rootfstype=ext4

initrd /boot/initrd.img-2.6.28.1-vmware-guest-server

quiet
```

2. Save and close the file. Now, run the command to update Grub:

```
# update-grub
```

3. Next, update your '/etc/fstab' file so that it can be mounted as an ext4 file system using the following command.

```
# vi /etc/fstab

Now, add the following code:
UUID=41c22818-fbad-4da6-8196-c816df0b7aa8 /boot ext4
defaults,errors=remount-ro,relatime
```

```
0 1
```