



Figure 1: Cacti's console tab

- 3 Import the Cacti database (included in a file called *cacti.sql* that is provided by Cacti) using the following command:

```
$ sudo cat cacti.sql | mysql5 -u root -p cacti
```

- 4 You can check if the required Cacti tables were created by using the following MySQL commands:

```
mysql> use cacti;
mysql> show tables;
```

- 5 Edit file *cacti/include/config.php* and update it with your MySQL related information. Mine is as follows:

```
/* make sure these values reflect your actual database/host/

user/password */
$database_type = "mysql";
$database_default = "cacti";
$database_hostname = "127.0.0.1";
$database_username = "cacti";
$database_password = "password";
```

- 6 Ensure Apache has access to and knows about the Cacti directory.

For the first task, both the user and group owners of the Cacti directory may need to be changed using the *chown* command. The user and the group of the Web server process should own the Cacti directory. For the second task, the Cacti directory should either be added inside the root directory of your Web server (defined by the *DocumentRoot* variable) or *httpd.conf* should know about it (using the *Alias* command).

- 7 Before setting up Cacti's *Poller* to run as a *cron* job, it must be run manually as follows and the output watched for possible error messages:

```
$ sudo -u www /usr/bin/php cacti/poller.php
```

```
06/28/2012 11:56:07 AM - POLLER: Poller[0] WARNING: Cron is
out of sync with the Poller Interval! The Poller Interval
```

Devices [new]	
General Host Options	
Description	
Give this host a meaningful description.	
Hostname	
Fully qualified hostname or IP address for this device.	
Host Template	Cisco Router
Choose the host Template to use to define the default Graph Templates and Data Queries associated with this host.	
Number of Collection Threads	1 Thread (default: 2)
The number of concurrent threads to use for polling this device. This applies to the Spine poller only.	
Disable Host	☐ Disable Host
Check this box to disable all checks for this host.	
Availability/Reachability Options	
Downed Device Detection	
The method Cacti will use to determine if a host is available for polling.	
NOTE: It is recommended that, at a minimum, SNMP always be selected.	
Ping Timeout Value	400
The timeout value to use for host ICMP and UDP ping. This host SNMP timeout value applies for SNMP traps.	
Ping Retry Count	1
After an initial failure, the number of ping retries Cacti will attempt before failing.	
SNMP Options	
SNMP Version	Version 1
Choose the SNMP version for this device.	
SNMP Community	public
SNMP read community for this device.	
SNMP Port	161
Enter the UDP port number to use for SNMP (default is 161).	
SNMP Timeout	500
The maximum number of milliseconds Cacti will wait for an SNMP response (does not work with php-mib2).	
Maximum OIDs Per Get Request	10
Specified the number of OIDs that can be obtained in a single SNMP Get request.	
Additional Options	
Notes	
Enter notes to this host.	

Figure 2: Adding the Cisco 877W router