



Figure 2: Node endpoint




Figure 3: Node metrics

You will notice that the node exporter has started to collect various metrics and has exposed a Prometheus metrics data compatible endpoint on port 9100. If we visit the endpoint `http://<your-node-ip>:9100`, you will see the node endpoint as shown in Figure 2.

Click on the **Metrics** link and it will display multiple metrics that are captured. A sample screenshot is shown in Figure 3.

Now that the node exporter is working fine, let us start the Prometheus server. Before we start the Prometheus server, we need to identify the nodes from which it will scrape the node metrics.

Go to the folder into which you extracted the core Prometheus server files, i.e., `prometheus` and `prometheus.yml`. The YAML file is the key configuration file and will define multiple targets that the Prometheus server needs to scrape. In addition to targets, it can also have multiple other configuration entries like alerts, default time intervals, etc.

Since we are only interested in monitoring one node, which is running locally for the moment, the `prometheus.yml` file is shown below:

```
#my global config
global:
  scrape_interval: 15s
  evaluation_interval: 15s
```

scrape_configs:

```
- job_name: 'node'
  static_configs:
    - targets: ['localhost:9100']
```

Now, let us launch the Prometheus server as shown below:

```
$ ./prometheus
INFO[0000] Starting Prometheus (version=1.5.0, branch=master,
revision=d840f2c400629a846b210cf58d65b9fbae0f1d5c)
source=main.go:75
INFO[0000] Build context (go=go1.7.4, user=root@a64ed5b536e3,
date=20170123-13:56:24) source=main.go:76
INFO[0000] Loading configuration file prometheus.yml
source=main.go:248
INFO[0000] Loading series map and head chunks...
source=storage.go:373
INFO[0001] 1203 series loaded.
source=storage.go:378
INFO[0001] Starting target manager...
source=targetmanager.go:61
INFO[0001] Listening on :9090
source=web.go:259
```

You can see that the Prometheus server is listening on port 9090, and we can use that information to take a peek into its default Web user interface (UI).

Visit the endpoint on port 9090 as shown in Figure 4.

You can now enter an expression for one of the metrics that you want to take a look at — for example, the node CPU metrics,




Figure 4: Prometheus server UI




Figure 5: Prometheus server graphs