

Figure 3: Console interface

To defragment the Firefox cache, use the following command:

```
udefrag "%APPDATA%\Mozilla"
```

To defragment the Google Earth cache, use the command given below:

```
udefrag "%APPDATA%\Google\GoogleEarth"
```

To defragment small files from all the non-removable




Figure 4: Graphical interface

disks, use the command given below:

```
cmd.exe /C "set UD_SIZELIMIT=100M && udefrag --wait --all-fixed"
```

Boot time defragmentation

To defragment any system file or file that is locked by the system or application, boot time defragmentation is used. Native UltraDefrag can process files before locking them as ordinary files. When the boot time defragmenter is enabled, it will run at every boot. To exit immediately, you can press any key when the program prompt is displayed. The boot time

Table 1: All available boot commands

Command	Usage
; or #	Lines starting with one of these characters are treated as comments.
@	Lines starting with this character will be not be shown on the screen.
boot-on	Turns the boot time defragmenter on for the next boot.
boot-off	Turns the boot time defragmenter off for the next boot.
call	Similar to the DOS command. Executes a script; if none is specified, the main boot time script will be executed.
echo	Similar to the DOS command. Displays a message, an empty line, sets whether the commands will be shown on the screen or not, or displays the current setting.
exit	Similar to the DOS command. Terminates UltraDefrag.
help	Lists all available commands.
hexview	Displays a file in a HEX viewer layout.
history	Lists all manually entered commands. To cycle through them, use the up/down arrow/cursor keys.
man	Lists or displays available manual pages.
pause	Pauses the script execution for the specified time interval (in milliseconds) or till a key is pressed if no duration is specified.
reboot	Reboots the computer.
set	Similar to the DOS command. Lists, sets and clears environment variables.
shutdown	Shuts the computer down.
type	Similar to the DOS command. Displays a file; if none is specified, the main boot time script will be shown.
udefrag	This is the boot time equivalent of the console interface. Accepts the following command line switches: -i, -la, -a, -o, -q, --quick-optimize, --optimize-mft, --all, --all-fixed, -r, --repeat. To process single files or directories, specify their absolute paths. If they include spaces, enclose them by double quotes.