



KNOW HOW



❶ I have created a virtual server using OpenVZ, on which I have installed CentOS 5.3 and MySQL 5.0.45. After installing MySQL I was unable to start mysqld because of the appearance of the following error, according to the log file: Fatal error: Can't open and lock privilege tables: Table 'mysql.host' doesn't exist". Please help me configure MySQL.

—Suraj Ghugtal, Lucknow

To overcome this issue you need to remove the MySQL datadir. You don't have to worry about the data as you have a new installation. Check the location of your mysql datadir in /etc/my.cnf—by default, it is /var/lib/mysql—and remove it:

```
# rm -fr /path_to_datadir
```

Now go to /usr/bin/ (or whatever your MySQL path is) and run the following commands:

```
/mysql_install_db --user=mysql --ldata=/sqldata
/mysql_safe --datadir=/sqldata --user=mysql &
```

This should resolve the issue.

❷ I was trying out the KDE 4.3-based opensUSE 11.1 implementation (LFY Sep'09 issue) and later installed it on a Dell Inspiron 1420 laptop. I would like to use the Reliance NetConnect USB on this laptop. However, I could not get any specific help on the Web or at forums.opensuse.org. I am hoping you will point me in the right direction. I have a Reliance Netconnect (CDMA 1x) ZTE / MG880 device. I was able to capture the dmesg output after I plugged-in and then unplugged the device.

```
usb 6-1: new full speed USB device using uhci_hcd and address 6
usb 6-1: configuration #1 chosen from 1 choice
```

```
usb 6-1: New USB device found, idVendor=19d2, idProduct=fffd
usb 6-1: New USB device strings: Mfr=1, Product=2, SerialNumber=3
usb 6-1: Product: ZTE CDMA Tech
usb 6-1: Manufacturer: ZTE, Incorporated
usb 6-1: SerialNumber: Serial Number
```

On un-plugging the modem, dmesg shows the following:

```
usb 6-1: USB disconnect, address 6
```

—R V Mishra, rajyav@hotmail.com

To connect and use your MG880 modem, follow the steps given below.

Open a terminal and switch to being the root user. Now run a modprobe:

```
# modprobe usbserial vendor=0x19d2 product=0xffff
```

You can find the product and vendor ID in your dmesg or by running the following command:

```
# cat /proc/bus/usb/devices
```

I assume that you have wvdial installed. Now just run:

```
# wvdialconf
```

After the successful completion of the command, check the /etc/wvdial file, which should have the following information:

```
Init1 = ATZ
Init2 = ATQ V1 E1 S0=0 &C1 &D2 +FCLASS=0
Modem Type = Analog Modem
Phone = #777
Username = <Put_your_phone_number_here>
Password = <Put_your_phone_number_here>
ISDN = 0
SetVolume = 0
FlowControl = Hardware (CRTSCTS)
Modem = /dev/ttyUSB0
Dial Command = ATDT
Baud = 460800
Stupid Mode = 1
```

Now run the wvdial command and wait for the modem to connect. **END**