

```

= This screen: help
[Disk] defaults to sdb for first 128 disk. [disk-part] defaults to sdb for
the whole first 128 disk. Run sdb for second 128 disk, sdb for first 32G
disk, etc. Default image for slurpdisk is 'rmbd.gz'.

[Copy] Send commands to backup/restore at
disk@at.pogoipfinger.de?
http://www.pogoipfinger.de/

p440 disk
p440 at slurmdb0 drive 0: (0000 HHHHHH)
p440 drive supports 128-sector PIO transfer, LBN addressing
p440: 151250 MB, 36440 cyl, 16 head, 63 sec, 512 bytes/sect x 167772160 sectors
p440: 32-bit data part
p440: drive supports 720 mode 2, 010a-00a mode 6 (010a-133)
p440 at slurmdb0 drive 1: (0000 HHHHHH)
p440 drive supports 128-sector PIO transfer, LBN addressing
p440: 151250 MB, 36440 cyl, 16 head, 63 sec, 512 bytes/sect x 167772160 sectors
p440: 32-bit data part
p440: drive supports PIO mode 1, 000 mode 2, 010a-00a mode 6 (010a-133)
p440p440d000000: using PIO mode 4, 010a-00a mode 2: 010a-00a (using 000)
p440p440d000000: using PIO mode 4, 010a-00a mode 2: 010a-00a (using 000)
p440: copy to sdb
p440: 100 256 42 888

```

Figure 4: Disk cloning in progress




Figure 5: Initial screen of partimage



Figure 6: Options to save the partition

7. slurpdisk restores a disk from the FTP image:

```
slurpdisk ftp-address:imagename
```

8. slurppart restores a partition from the FTP image:

```
slurppart ftp-address:imagename disk-part
```

It is preferable to run `gdu` in a DHCP-enabled network if FTP transactions are planned. If DHCP is not available, the network needs to be set up manually.

Partimage for back up/restore

Consider the following scenario. You have installed a Linux distribution that comes with minimal packages. Additional packages have been installed from the Internet using a package manager. So, patiently, you've updated and customised the OS according to your needs. Now your friend does not have an Internet connection and needs all these additional packages on his system. Or, all of a sudden, the OS has crashed, and you don't have enough time or resources to repeat all the steps.

Under the circumstances, back up your partitions every time you update your system—this back-up can be shared with any other system or used to restore the OS when it crashes.

Partimage helps you with these kinds of back-ups. It can be installed on many distros via package managers or, preferably, you can run it off a live CD. It is a part of the System Rescue CD.

Here's how you back up a partition:

1. Run the **partimage** command from a terminal.
2. Select partitions for which a back-up needs to be taken.
3. Specify the image name along with a suitable path. Another partition/removable disk has to be mounted in order to store the image in it. (In case of single partitions, or if none of the additional partitions have enough free space, you can use NFS- and Samba-shared mounts to save images on a remote computer.)
4. Opt for 'Save partition...' and go to the next screen (short cut: F5).
5. In the next screen, select the compression level, split mode and finish with other default options (Figure 6). Split mode (auto) means that when a volume in which the image is being stored is full, the image is split into multiple parts. Otherwise, fixed size parts can also be created for the convenience of storing on CDs/DVDs.
6. You'll be prompted to give a description of the image for later use, and one more confirmation screen before copying starts.
7. The copying process will start now. Options are available to cancel, pause and resume the operation.
8. A confirmation screen appears after the completion of the process.

The following are the steps for restoring a partition:

1. Run partimage and choose the partition that needs to be restored.
2. Give a path to the image (from a mounted partition/removable disk).
3. Opt for 'Restore Partition...' and go to the next screen (shortcut: F5).
4. Opt for defaults and hit 'Continue' (F5).
5. Now, the image description should appear, which is given at the time of backup, and one more confirmation screen before restore starts. Figure 7 shows a typical restoration in progress.
6. A confirmation screen appears after completion of the process.

Note: When restoring an image, the size of the partition that's being restored should be greater or equal to the size of the original partition on which the backup is taken. However, the target partition is accessible up to the size of the original partition only, in case it is larger. Even though the image size is smaller with only used blocks, the target partition can't be smaller than the original one.