

replot 'meminfo' using 1:6 title "CACHED MEMORY" with lines

Save this as `myfree.gplot`. Now run the command: `gnuplot-persist myfree.gplot`

`gnuplot` will display a graphical view of the memory consumption trend as shown in Figure 7.

In the same manner, we can also display the graph for the disk activities, etc.

SNMP and MRTG

MRTG (Multi Router Traffic Grapher) can be a very handy tool for monitoring network traffic passing through each and every interface of your server. So when you finish monitoring your network traffic, you can configure your network as per your performance needs—which we will be discussing later.

Configuring MRTG is fairly simple. As MRTG polls SNMP (Simple Network Management Protocol) agents, we should first configure SNMP. Remember that MRTG works with Apache, so make sure you install that as well. Here is an MRTG configuration for reference. I am configuring my FTP server that we had used for MRTG. I am using it intentionally so that we have some real network traffic.

First, install SNMP, MRTG and Apache on the system using your package manager. Now, allow the SNMP through `tcp-wrapper`. Edit `/etc/hosts.allow` and write `snmpd: ALL` to allow SNMP.

Use the `snmpconf` tool to create at least one SNMP community. In the first step, choose `/etc/snmp/snmpd.conf`. Make sure you are inside the `/etc/snmp/` directory before running `snmpconf`:

The following installed configuration files were found:

1: `/root/.snmp/snmp.conf`

Would you like me to read them in? Their content will be merged with the output files created by this session.

```
Linux 2.6.18-52.el5xen (server1.example.com) 08/13/09
```

kbmemfree	kbmemused	%memused	kbuffers	kbcache	kbswapfree	kbswapused	%swapused	kbpgcad
429004	2405300	85.28	292468	1761064	4096392	140	0.00	140
429004	2405300	85.28	292468	1761064	4096392	140	0.00	140
429004	2405300	85.28	292468	1761064	4096392	140	0.00	140
429004	2405300	85.28	292468	1761064	4096392	140	0.00	140
429128	2405176	85.28	292492	1761064	4096392	140	0.00	140
429128	2405176	85.28	292500	1761064	4096392	140	0.00	140
429128	2405176	85.28	292500	1761064	4096392	140	0.00	140
429128	2405176	85.28	292500	1761064	4096392	140	0.00	140
429128	2405176	85.28	292500	1761064	4096392	140	0.00	140
429252	2405052	85.27	292536	1761064	4096392	140	0.00	140
429252	2405052	85.27	292524	1761064	4096392	140	0.00	140

Figure 6: Memory information output using `smr`




Figure 7: The graphical view of the memory consumption using `gnuplot`

Valid answer examples: "all", "none", "3", "1,2,5"

Read in which (default = all): 1

In the next step, select `snmpd.conf`. Then select Access Control Setup.

The configuration information which can be put into `snmpd.conf` is divided into sections. Select a configuration section for `snmpd.conf`

that you wish to create:

- 1: Access Control Setup
- 2: Extending the Agent
- 3: Monitor Various Aspects of the Running Host
- 4: Agent Operating Mode
- 5: Trap Destinations

8: System Information Setup

Other options: finished

Select section: 1

In the next option, select "SNMPv1/SNMPv2c read-only access community name". When prompted for the name, give the community name as 'networknats' (or anything you like).

Select from:

- 1: a SNMPv3 read-write user
- 2: a SNMPv3 read-only user
- 3: a SNMPv1/SNMPv2c read-only access community name
- 4: a SNMPv1/SNMPv2c read-write access community name