



Figure 5: Auth key




Figure 6: Spacewalk client

```
#spacewalk-setup --disconnected --external-oracle
```

If you want to use Postgre-sql from another server, use the command shown below:

```
#spacewalk-setup --disconnected --external-postgresql
```

While setting up, you will be asked a few questions like the ones below or you can create an answer file for this.

```
#spacewalk-setup --disconnected --answer-file=<answer file>
admin-email = root@localhost.com
ssl-set-org = spacewalk.org
ssl-set-org-unit = spacewalk
ssl-set-city = chennai
ssl-set-state = Tamilnadu
ssl-set-country = India
ssl-password = walker2
ssl-set-email = root@localhost
ssl-config-sslhost = Y
db-backend=oracle
db-name=spaceschema
db-user=spaceuser
```

```
db-password=password1
db-host=localhost
db-port=1521
enable-tftp=Y
```

Restart the service by issuing the following command:

```
#/usr/sbin/spacewalk-service restart
```

That's it. We have done the installation, so let's proceed to the configuration part.

1. Open Spacewalk from the URL <https://<SpacewalkServer FQDN>/>.
2. Once opened, you will get a screen to create the admin user. Once logged in, you will get an overview screen like what's shown in Figure 2.
3. Now let's look at preparing the Spacewalk server to install the OS on clients. For that, the first step is creating the channel, which holds the repository.

From the Web GUI, go to 'Channels==>Manage Software Channels ==> Create channel' as in Figure 3. Fill all the text boxes and create a channel.

You can create a channel via the command line as follows:

```
#/usr/bin/spacewalk-common-channels -v -u admin
-p password -a 1386,x86_64 -k unlimited 'centos6*'
'spacewalk-client'
```

4. Next, we need to create a repo on this channel and sync it with the DVD or from existing repos. Let us create a repo as per Figure 4, by going to Channels -> Manage Software Channels -> Manage Repositories -> Create new repository. As shown in the figure, I used my DVD repo from file:///mnt/.
5. Next, we need to create a link to a software channel as follows: Channels -> Manage Software Channels -> [channel name] -> Repositories -> [Repository to be linked to the channel] -> Update Repositories. Start/sync the repo by clicking on the Sync tab.
6. Create an activation key as shown in Figure 5 (Systems > Activation Keys > Create Key) with the new base channel. When creating a registration key for testing, always use a human readable format so that it will be easy while configuring agents. Of course, it is not recommended for a production environment. We need these keys to register clients with the Spacewalk server.

We now come to the end of the server configuration. We will now start configuring clients.

1. Create repos pointing to Spacewalk repos by installing the following RPMs:

```
# rpm -Uvh http://yum.spacewalkproject.org/2.3-client/RHEL/6/
```