

Figure 1: Version update




Figure 2: pfSense in dual WAN

pfSense dual WAN failover configuration steps

1. Configure two WAN interfaces
2. Establish dual WAN group
3. Add firewall rules required for the dual WAN set-up
4. Reconfigure Squid Proxy service
5. Configure default gateway auto failover
6. Best practice: Configure DNS servers

Configuring pfSense 2.3 dual WAN failover

1. **Configure two WAN interfaces:** In Figure 2, labels in blue indicate names of pfSense interfaces.

Verify that LAN and primary internet connections are connected to corresponding pfSense LAN and WAN interfaces. Now, connect standby internet connection to OPT1 interface.

Configure OPT1 interface's ISP settings. pfSense supports various types of Internet connections such as




Figure 3: OPT1 PPPoE configuration

PPPoE, static, DHCP, etc. The PPPoE connection is used in this test set-up.

As you may be aware, many ISPs allow Internet connections to be terminated on only one device by binding the device's MAC address. Thus, the user is required to call ISP and reset MAC address before configuring the internet with different device.

Here, an interesting feature of pfSense — 'MAC control' comes handy. This field can be used to configure (spoof) MAC address to the one registered with ISP and configure the internet connection without unnecessary hassle of coordinating with ISP.

2. **Establish a dual WAN group:** Once the firewall is