

Step 1: Download Apache Cassandra

To get started with you download, select a DataStax Distribution of Apache Cassandra installer from the table below

	v3.2.1	v3.1.1
Unix & Mac OS X 10.x	Tarball	Tarball
Windows Server 2008/2012 or Windows 7/8 (64-Bit)	MSI Installer (64-bit)	MSI Installer (64-bit)
Red Hat Enterprise Linux / CentOS 6.5 or Later	Tarball	Tarball
	RPM Using Yum	RPM Using Yum
Latest Ubuntu LTS or Debian Stable	Tarball	Tarball
	DEB Using Apt-Get	DEB Using Apt-Get

Figure 1: Download Apache Cassandra

ii. Verify the installation using *nodetool*:

```
C:\> "C:\Program Files\DataStax-DDC\apache-cassandra\bin\
nodetool status
```

The expected output is:

```
Datacenter: datacenter1
=====
Status=Up/Down
|/ State=Normal/Leaving/Joining/Moving
-- Address Load Tokens Owns Host ID
Rack
UN 127.0.0.1 133.97 KB 256 ? 16e04c60-5d43-
4372-9e71-7acdcaa023bc rack1
```

If you still find an error in displaying the *nodetool status*, then check the *JAVA_HOME* env variable path. It should point to your Java installation (e.g., *C:\Program Files\Java\jdk1.8.0_51*).

Multi-node cluster configuration

In the previous section, I have described the installation on a single node. In this section, I will cover the setting up of Cassandra Multinode (same data centre).

The prerequisites are:

- Install same versions of Cassandra on all nodes
- Get the IP address of each node
- Change the default cluster's name

Installation steps

- If Cassandra is running, stop it and clear the data.




Figure 2: Windows programs installed by DataStax Distribution




Figure 3: Set JAVA_HOME environment variable path

- To stop Cassandra, use the following command:

```
$ sudo service Cassandra stop
```

- To clear data, use the command given below:

```
$ sudo rm -rf /var/lib/cassandra/data/system/*
```

- Prepare *cassandra.yaml* on all nodes and restart Cassandra.

Change to the *config* properties that we need while setting up the multinode cluster.

num_tokens: This defines the number of tokens randomly assigned to this node on the ring. The default value is 256.

-seeds: Cassandra nodes use this list of hosts to find each other and learn the topology of the ring. We must change this if we are running multiple nodes.

listen_address: If not set, Cassandra asks the system for the local address, the one associated with its host name. In some cases, Cassandra doesn't produce the correct address and you must specify the *listen_address*.

endpoint_snitch: This is the name of the snitch.

As an example, we have installed Cassandra into three nodes -- 110.82.155.0, 110.82.155.1 and 110.82.155.2, of which two are seed nodes (110.82.155.0 and 110.82.155.2).

```
cluster_name: 'MultinodeTestCluster'
num_tokens: 256
seed_provider:
  - class_name: org.apache.cassandra.locator.
SimpleSeedProvider
  parameters:
    - seeds: "110.82.155.0,110.82.155.2"
listen_address:
rpc_address: 0.0.0.0
endpoint_snitch: GossipingPropertyFileSnitch
```

- Write the appropriate rack and data centre name *cassandra-rackdc.properties*: