




COVERING AND INSERTING PIPING CORD




1 Prepare bias strips approximately 4cm (1½in) wide (see pp.46–47). Fold the bias cut fabric strip in half, wrong side to wrong side, over the piping cord. Pin or tack in place.



2 Machine stitch in place close to the cord using a zip foot or special piping foot. If the zip foot doesn't run smoothly against the covered cord, tack the fabric in place before machine stitching.




3 Trim the seam allowance on the piping cover so that it is the desired seam allowance width – it can be less than this width, but not more. Align the seam on the piping cover with the intended seamline on the right side of the front of the fabric and pin. Tack in place with the piping facing inwards.



4 If you are sewing the piping around a corner, bend it carefully to form a 90-degree angle and continue tacking.

5 Place the back fabric piece over the front piece with the right sides together and pin. Using a zip foot, machine stitch the layers together, stitching on top of the piping cord seam.



6 Turn the piece right-side out and carefully press the fabric away from the piping.