




9 Piece the backing (see p.45) then lay the backing on a large, clean, flat surface with the wadding on top. Smooth out the two to make sure they are not bunched or folded, then lay the quilt top on the wadding (see p.44). The wadding and backing fabric will both extend slightly beyond the edges of the quilt top. Starting from the centre and working outwards, pin all three layers together using safety pins. Make sure that all the layers lie flat and check that the underside of the backing fabric also lies flat.




10 Quilt the top according to your preference. Here, we have quilted in the ditch (see p.135) along every sixth strip. Roll up the end of the quilt in the throat area of the sewing machine to keep it out of the way as you work (see p.134). Remove any safety pins that get in the way as you work.



11 Using the quilter's ruler and the rotary cutter, trim away the excess wadding and backing fabric from the edges of the quilt.



12 Attach the bias tape, if used, to the edge of the quilt following the instructions on pages 48–49. Or, create a 7.5cm (3in) wide double-fold binding strip from fabric and attach it using the Double-fold binding technique on page 51.



13 Fold the binding to the back of the quilt, pin it in place, then sew it by hand slip stitching it in place (see p.49).