


## ► BINDING WITH PRE-MADE BIAS BINDING

Every quilt will need some form of binding to finish the raw edges and a pre-made bias binding, or bias tape, is a quick and easy way to do this. Bias tape can be used on small projects and projects that will not receive a lot

of wear, such as wall hangings. Steps 3–8 show how to mitre a corner when binding. Mitring should be used when attaching any binding around a corner.




**1** After squaring up the quilt, measure all four sides, add them together, then add approximately 40cm (16in) to the total length. Cut the bias tape to this final measurement. Open up the long, folded edges of the bias tape and with right sides together, align the bias tape along one side of the quilt top, starting in the middle of the side, not a corner. Pin in place.



**2** Beginning a few centimetres (inches) from the end of the bias tape, with the quilt right side up, stitch along the outside edge of the tape through all the layers. Use a seam allowance that is one-quarter the width of the open bias tape. The stitch should land approximately on the open fold of the binding.



**3** Carefully stitch along the edge stopping a seam allowance's distance from the corner. Back stitch a few stitches.



**4** Remove the quilt from under the machine foot, but do not cut the threads or pull it out too far.



**5** Create a mitred corner by folding the tape 45-degrees to the right of the quilt top. The tape should run parallel with the bottom edge of the quilt.