

<https://192.168.XXX.XX>

You will get the installation wizard and you can immediately start storing all your data, which you can access anytime remotely. Now, your ownCloud will be as shown in Fig. 3.

Your own BitTorrent set-up

If you download a lot, then it is better to have a separate device such as Raspi, which can download for you




Fig. 4: Add Host window




Fig. 5: Connection Manager window




Fig. 6: Deluge window

all the time. If you do it on your laptop, it consumes much more power. You also do not want to run your laptop 24x7.

You do not need to run an update and upgrade; we have covered that in the previous section. But, if you are setting up BitTorrent alone, just run those commands once again. Then, install Deluge, a lightweight cross-platform BitTorrent client.

To install Deluge, give the following commands:

```
$ sudo apt-get install deluge
$ sudo apt-get install deluge-console
```

Run Deluge and stop it using the commands given below. Similarly, create the default configuration file, which can be created when Deluge runs for the first time.

```
$ deluge
$ sudo kill deluged
```

Open the configuration file:

```
$ sudo nano ~/.config/deluge/auth
```

Add the following line to it, then save and exit:

```
pi@raspberrypi:~$
```

(This will give full access to user pi. And the password will be raspberry.)

Start Deluge and Deluge Console again to change the configuration:

```
$ deluge
$ deluge-console
```

You will see a Deluge Console window now. Make the following changes:

```
config --s allow_remote True
config allow_remote
```

(This is done to check if the value changed successfully.)

```
exit
```

Restart Deluge for the changes to take effect:

```
$ sudo kill deluge
$ deluge
```

Install Deluge on your computer to connect to the one running on Raspi.

This way, you can initiate all downloads from your computer and Raspi will take care of the rest. I use Ubuntu on my personal computer but you can also do it on Windows. Steps given below are for an Ubuntu system.

Install Deluge:

```
$ sudo apt-get install deluge
```

Once installed, run it and make some simple changes.

Go to Preferences > Interface in Raspi and uncheck Enable under Classic mode. Press OK and restart the client (Ubuntu).

This time you will get Connection Manager on the screen. From here, you can create a connection to Deluge running on Raspi. You will get Add Host dialog box as shown in Fig. 4. Click Add and create a new connection. Enter the IP, username and password.

```
IP - 192.168.xx.xx
User name - pi
Password - raspberry
```

After successful connection, the screen will look as shown in Fig. 5.

Click Connect to connect to Deluge Demon on Raspi. You will see Deluge screen as shown in Fig. 6.

(Note that if you are on proxy, you need to configure it separately. For that, go to Preference > Proxy and change the settings. Do not forget to restart the client every time you make changes in the settings.)

Now, you are ready to go. Down-