## Part I Syllabus - Fundamental Underlying Layers

Date	Subject	File
Week 1: 9/Jan/2023 11/Jan/2023	Introduction: course logistics and Internet history	M1-L1-Introduction.pptx
	Layered Network Architecture	First part of M1-L2-Network Layer & Physical Resilience.pptx

Second part of M1-L2-Network Layer &

Physical Resilience.pptx

M1-L3-DLL-Flow Control.pptx

M1-L4-DLL-Error Control.pptx

M1-L5-LAN-Introduction.pptx

First part of M1-L7-LAN-Ethernet.pptx

Second part of M1-L7-LAN-Ethernet.pptx

M1-L6-LAN-MAC.pptx

M1-L8-LAN-WLAN.pptx

M1-L10-Paradigms.pptx

M1-L10-Paradigms.pptx

M1-L9-Mobile.pptx

Physical Layer: Network Resilience

Data link layer – Flow control

Data link layer – Error control

Local area network – MAC

Local area network – Ethernet

Local area network – WLAN

E-learning for Network paradigms

Mobile Access Networks

Network paradigms

Local area network – Ethernet Evolutions

Local area network - Introduction

Week 2.

Week 3:

Week 4:

Week 5:

Week 6:

Week 7:

16/Jan/2023

18/Jan/2023

25/Jan/2023

30/Jan/2023

01/Feb/2023

06/Feb/2023 08/Feb/2023

13/Feb/2023

15/Feb/2023

20/Feb/2023

22/Feb/2023

#### Additional Materials

The related content talked today in

https://eclass.teicrete.gr/modules/document/file.php/TP326/%CE%98 %CE%B5%CF%89%CF%81%CE%AF%CE%B1%20(Lectures)/Compute r Networking A Top-Down Approach.pdf is as follow:

- Circuit Switching: Page 27 Page 32
- Packet Switching: Page 22 Page 27
- Delay, Loss and Throughput: Page 35 Page 47
- You can also find other video materials about
  - Switching Techniques <a href="https://www.youtube.com/watch?v=-HIJ4psu5aU">https://www.youtube.com/watch?v=-HIJ4psu5aU</a>
  - Delay <a href="https://www.youtube.com/watch?v=wo3M5G9ZHo0">https://www.youtube.com/watch?v=wo3M5G9ZHo0</a>



## How do you get your water?











## SC2008/CZ3006/CE3005 Computer Network

# Lecture 10 Network Paradigms (Not Examinable)





#### Contents

#### Data Transmission Technologies

- Network Design Approaches
- Circuited Switched Network
- Packet Switched Network
- Connection-Oriented vs Connectionless

#### Delay in Packet Switched Network

- Delay components in packet switched network
- Transmission delay calculation
- Pipeline



## Data Transmission Paradigms




#### Overview

- Networks are used to interconnect many devices: LAN/WAN
- Now, wide area networks
  - Since the invention of the telephone, circuit switching has been the dominant technology for voice communications.
  - Since 1970, packet switching has evolved substantially for digital data communications. It was designed to provide a more efficient facility than circuit switching for bursty data traffic.
    - Two types of packet switching:
      - Datagram (such as today's Internet)
      - Virtual circuit (such as Frame Relay, Asynchronous Transfer Mode (ATM))



## Network Design



#### **Approach 1: Smart intermediate nodes & dumb end systems**

- E.g., telecommunication networks
- Achieve very complex traffic management but difficult to upgrade

#### **Approach 2: Dumb intermediate nodes & smart end systems**

- E.g., the Internet
- Attract innovation at applications but difficult to manage traffic



## (Intermediate) Switching Nodes

- Nodes may connect to other nodes, or to some stations.
- Network is usually partially connected
  - However, some redundant connections are desirable for reliability
- Two different switching technologies
  - Circuit switching
  - Packet switching



## Communication Networks Taxonomy

#### **Communication Networks**

Circuit Switched (Telephone Calls)

Packet Switched (Data Communications)

Virtual Circuit Switching (Connection Oriented) eg. X.25, ATM, etc

Datagram Switching (Connectionless) eg. Internet




## Circuit Switching

#### Circuit switching:

- There is a dedicated communication path between two stations (end-to-end)
- The path is a connected sequence of links between network nodes. On each physical link, a logical channel is dedicated to the connection.
- Communication via circuit switching has three phases:
  - Circuit establishment (link by link)
    - Routing & resource allocation (FDM or TDM)
  - Data transfer
  - Circuit disconnect
    - Deallocate the dedicated resources
- The switches must know how to find the route to the destination and how to allocate bandwidth (channel) to establish a connection.



# Public Switched Telephone Network (PSTN)



Subscriber loop: the link between the subscriber and the network.

Exchanges: the switching centers in the network.

End office: the switching center that directly supports subscribers.

Trunks: the branches between exchanges. They carry multiple voice-frequency circuits using either FDM or synchronous TDM.



## Packet Switching Principles

#### Problem of circuit switching

- Designed for voice service
- Resources dedicated to a particular call
- For data transmission, much of the time the connection is idle (say, web browsing)
- Data rate is fixed
  - Both ends must operate at the same rate during the entire period of connection
- Packet switching is designed to address these problems.



## **Basic Operation**

#### Data are transmitted in short packets

- Typically at the order of 1000 bytes
- Longer messages are split into series of packets
- Each packet contains a portion of user data plus some control info

#### Control info contains at least


 Routing (addressing) info, so as to be routed to the intended destination

#### Store and Forward

 On each switching node, packets are received, stored briefly (buffered) and passed on to the next node.



## Use of Packets





## Advantages of Packet Switching

#### Line efficiency

- Single node-to-node link can be dynamically shared by many packets over time
- Packets are queued up and transmitted as fast as possible

#### Data rate conversion

- Each station connects to the local node at its own speed
- In circuit-switching, a connection could be blocked if there lacks free resources. On a packet-switching network, even with heavy traffic, packets are still accepted, yet causing an increased delay.

#### Priorities can be used

 On each node, packets with higher priority can be forwarded first. They will experience less delay than lower-priority packets.



## Packet Switching Technique

- A station breaks long message into packets
- Packets are sent out to the network sequentially, one at a time
- How will the network handle this stream of packets as it attempts to route them through the network and deliver them to the intended destination?
  - Two alternative approaches
    - Datagram approach
    - Virtual circuit approach




## Datagram

- Each packet is treated independently, with no reference to packets that have gone before.
  - Each node chooses the next node on a packet's path.
- Packets can take any possible route.
- Packets may arrive at the receiver out of order.
- Packets may go missing.
- It is up to the receiver to re-order packets and recover from missing packets.
- Example: Internet



## Datagram

- Each packet carries the full destination address.
- Each packet is treated independently.
- Packets may arrive out of sequence.
- Packets are called datagrams.





### Virtual Circuit

- In virtual circuit, a pre-planned route is established before any packets are sent, then all packets follow the same route.
- Each packet contains a virtual circuit identifier instead of destination address, and each node on the pre-established route knows where to forward such packets.
  - The node need not make a routing decision for each packet.
- Example: X.25, Frame Relay, ATM




### Virtual Circuit

A route between stations is set up prior to data transfer.

All the data packets then follow the same route.

But there is no dedicated resources reserved for the virtual circuit! Packets need to be stored-and-forwarded.





## Virtual Circuits v Datagram

#### Virtual circuits

- Network can provide sequencing (packets arrive at the same order) and error control (retransmission between two nodes).
- Packets are forwarded more quickly
  - Based on the virtual circuit identifier
  - No routing decisions to make
- Less reliable
  - If a node fails, all virtual circuits that pass through that node fail.

#### Datagram

- No call setup phase
  - Good for bursty data, such as Web applications
- More flexible
  - If a node fails, packets may find an alternate route
  - Routing can be used to avoid congested parts of the network



# Comparison of communication switching techniques


Circuit Switching	Datagram Packet Switching	Virtual Circuit Packet Switching
Dedicated transmission path	No dedicated path	No dedicated path
Continuous transmission of data	Transmission of packets	Transmission of packets
Fast enough for interactive	Fast enough for interactive	Fast enough for interactive
Messages are not stored	Packets may be stored until delivered	Packets stored until delivered
The path is established for entire conversation	Route established for each packet	Route established for entire conversation
Call setup delay; negligible transmission delay	Packet transmission delay	Call setup delay; packet transmission delay
Busy signal if called party busy	Sender may be notified if packet not delivered	Sender notified of connection denial
Overload may block call setup; no delay for established calls	Overload increases packet delay	Overload may block call setup; increases packet delay
Electromechanical or computerized switching nodes	Small switching nodes	Small switching nodes
User responsible for message loss protection	Network may be responsible for individual packets	Network may be responsible for packet sequences
Usually no speed or code conversion	Speed and code conversion	Speed and code conversion
Fixed bandwidth	Dynamic use of bandwidth	Dynamic use of bandwidth
No overhead bits after call setup	Overhead bits in each packet	Overhead bits in each packet



## Packet Transmission Time




## Delay in Packet Switched Networks





## Pipeline Effect






## Packet Transmission Time: Overhead vs. Pipeline

#### **Example:**

3 hops & 4 fragments

 $\therefore \text{Tx time} = 4 T_{frame} + (3-1) T_{frame}$ 



#### In general:

Tx Delay

- = Tx Delay of all packets in first hop
  - + (# of hops-1) \* Tx Delay of 1 packet

To find the optimum packet size, other delays should also be considered:

- Processing Delay
- Queueing Delay
- Signal Propagation Delay




## Packet Size (Transmission Time Consideration)

- Example 1: A packet of size 1000 bits would have transmission delay of 100 msec on a 10 Kbps link.
- Example 2: Consider a VC from node S to D through an intermediate node I (two hops). Link rate = 8 bps. Message is of 30 bytes. Header of a packet is 3 bytes.
  - Case-1: Message is transmitted as a single packet.
     Tx. Delay = 33 bytes \* 2 packet Txs / link rate = 66 sec
  - Case-2: Message is transmitted in 2 packets.
     Tx. Delay = 18 bytes \* 3 packet Txs / link rate = 54 sec
  - Case-3: Message is transmitted in 3 packets.
     Tx. Delay = 13 bytes \* 4 packet Txs / link rate = 52 sec
  - Case-4: Message is transmitted in 6 packets.
     Tx. Delay = 8 bytes \* 7 packet Txs / link rate = 56 sec



## Transmission Time



## Learning Objectives

#### Data Transmission Technologies

- Understand difference between circuit and packet switched networks
- Understand difference between datagram and virtual circuit switching

#### Delay in Packet Switched Networks

- Understand delay components in PSN
- Calculate packet transmission delay

