


Change View

It is possible to switch between different Views on the same Panel on the same Screen.


See the **PortalTab_example** Screen in the image below. It displays different Views (PortalGrid, PortalTree, see [View Templates](#)) on the same Panel on the same Screen. The Views are changed in runtime after selecting different tabs.



Change View Configuration

1. In this example Screen, two (or more) Views can be linked to one Panel.

Note that you cannot link the same View as the default View and a **Change View**.




2. Define which Action changes which View on the **content** Panel.

- ▷ The **GRID_TAB** Action changes the View to **PortalGrid** on the **content** Panel



- ▷ The **TREE_TAB** Action changes the View to **PortalTree** on the **content** Panel



For further exploration of the configuration, open **PortalTab_example** and look at the configuration:

Code / Description:	Revision:	Status:	Type:	Subtype:	Modified:	Unused for:
PortalTab				N/A		0 Days
PortalTab	APR.TPL.001.000	View	General	Cancelled	Yes	
PortalTab_example	APR.EXA.001.000	Screen	General	Cancelled	No	
PortalTab_example	APR.EXA.002.001	Screen	General	Active	Yes	
PortalTabNotification	APR.TPL.001.000	View	General	Cancelled	Yes	
PortalTabNotification	APR.TPL.002.001	DFC	View	Active	Yes	
PortalTabNotification_example	APR.EXA.001.000	Screen	General	Cancelled	No	
PortalTabNotification_example	APR.EXA.002.001	Screen	General	Active	Yes	
PortalTabWindow	APR.EXA.002.001	Layout	General	Active	Yes	

Change View Advanced Configuration

You can change a View with the use of the **On Initialize** or **On Load** DFCs. This scenario is applied when there is a need to show a View that can be determined only during runtime.


On Initialize and **On Load** DFCs have special Outputs: **PanelList** and **ViewList**. The **PanelList** Output should contain Screen Panel names in which corresponding items from the **ViewList** Output will be shown.

When the business logic returns a View name that is attached to a Screen as a Change View, its configuration will be displaying this View. When a View name is not found in the Screen configuration, a plain View configuration will be used.


Example:

If your **On Initialize** DFC returns those two Outputs with the values set as below:

In configuration when Views are available in Entity Manager:



In configuration when Views are entities that belong to the same Project:



Then the runtime will render the Screen where:

- ▶ View of Name "1" will be displayed in Panel of Name "A"
- ▶ View of Name "2" will be displayed in Panel of Name "B"
- ▶ View of Name "3" will be displayed in Panel of Name "C"

Then the runtime will render the Screen where:

- ▶ View of Name "1" that belongs to the Project of Code "Project1" will be displayed in Panel of Name "A"
- ▶ View of Name "2" that belongs to the Project of Code "Project1" will be displayed in Panel of Name "B"
- ▶ View of Name "3" that belongs to the Project of Code "Project1" will be displayed in Panel of Name "C"


Views that are not a part of the Screen configuration will not be attached to GPM packages automatically and must be added manually.

Business Example:

Assume that there is one Panel on the Screen that is displaying Alerts. Each Alert type has a corresponding View displaying it.

1. Create a Determination that keeps the link between specific View and a corresponding Alert type.
For each Alert, there is a View that can show the Alert detail and allow you to respond to that items.
2. Create a generic Screen with one Panel (in our example it name is set the ALERT_CONTENT) which will show the specific View depending on the Alert type.
3. Configure the OnLoad DFC configuration as follows:

- The first Function: the value of Alert type is taken from the [Portal Session](#).
- The second Function (BusinessLogic) based on the Determination configuration returns the View name for a given Alert type.
- The third Function sets the ViewList and Panellist Outputs.



Panellist and ViewList should be lists of the same number of elements.

After selecting the Alert from the list, you are able to show different Views for different Alert types which are not tied to the Screen configuration.