


How to Create a Layout


When creating a Layout, the Panels must be divided in the correct order. See the example below to understand the Layout creation logic.

1. Create a new Layout. Use one of the following options:
 - ▶ Select the **New...** option from the **File** drop-down in the **Main Menu**
 - ▶ Click  (New) on the **Toolbar**
 - ▶ Use **Ctrl+N** **Keyboard Shortcut**
 - ▶ Select **New > Layout** from the **Right-Click Menu** in the Entity Manager
2. Define the Layout look (see the [Layout Definition Example](#) section below).
3. Link a Default View to the last Panel (in this example, the CONTEXT_RIGHT Panel) using the **Default View** section on the Panel **Properties** pane.



After using this Layout on the Screen, you can see the Panel with this View linked.

4. Link a Header to the Layout using the **Default Header** section on the Layout Properties pane.




After using this Layout on the Screen, you can see the Screen with the Header linked.

Views can only be linked to the Panel elements that do not have any child elements.

Layout Definition Example

Design the following Layout:



In this Layout, there are four Panels for showing the Views:


- ▶ TABS: 100% x 100px
- ▶ CONTEXT_LEFT: 70% x auto
- ▶ CONTEXT_RIGHT: auto x auto
- ▶ FOOTER: 70% x 200px

The child Panel size is always in relation to its parent. For example, if the parent Panel width is 1000px and you create a child Panel of 70%, its width will be 700px. If this child Panel is divided further into two child Panels of 50%, their width will be 350px.


The steps below present how to divide and size Panels in order to obtain the Layout above.

Step 1

Start from the base panel, which is stretched to the full screen:




1. Right-click the previously created Layout in **Entity Explorer** and select the **Add Panel** option:



2. Set the following properties in the Layout Properties tool pane:

- ▶ **Name** – 2VPAN_FTR
- ▶ **Height, Fill** (fill full Screen)




Step 2

Divide the Panel created before into two child Panels:



1. Create two Sub-Panels under the 2VPAN_FTR Panel:



2. Set the following properties of the created Panels:


a. Panel 1:

- ▷ **Name:** TABS
- ▷ **Height, Specific:** 100px (height, as the parent is vertical)


b. Panel 2:

- ▷ **Name:** CONTEXT
- ▷ **Height, Fill** (fill rest of the space)

3. Set the 2VPAN_FTR Layout's orientation type to **Vertical** on the Layout Properties pane:




Step 3




When you have multiple Panels on one level, only one of them can have an undefined size. This means that it will always be the part of the Screen that is not taken by the other Panels (which must have their sizes defined).

1. Create two Panels under the CONTEXT Panel.
2. Set the following properties of created Panels:
 - a. Panel:
 - ▷ **Name:** CONTEXT_LEFT
 - ▷ **Height, Specific:** 70% (width, as parent is vertical)
 - b. Panel:
 - ▷ **Name:** CONTEXT_RIGHT
 - ▷ **Height, Specific:** 30%
3. Set the CONTEXT Panel orientation type to **Horizontal** on the Layout **Properties** pane.



Step 4



1. Create two Panels under the CONTEXT_LEFT Panel.
2. Set the following properties of created Panels:
 - a. Panel:
 - ▷ **Name:** CONTEXT_TOP_LEFT
 - ▷ **Height, Fill** (fill rest of the space)
 - b. Panel:
 - ▷ **Name:** FOOTER

▷ **Height, Specific:** 200px (height, as parent is horizontal)

3. Set the CONTEXT_LEFT Panel Orientation type to **Vertical** on the Layout Properties pane.

