

Input Source: User

General Tab

The general properties available for all inputs are described in the [Input Properties](#) topic.

Properties

General | **Advanced UI**

Name: Input1

Description:

Data Type: Char

Char

☒ Char ☒ Scalar

☐ Integer ☐ List

☐ Decimal ☐ List (Iterate)

☐ Boolean ☐ List (Duplicate)

☐ DateTime

☐ Complex

☒ Use Source Value Copy

Input Source: User

User Interface Control: Text

☐ Allow external input

External input name: Input1

Dictionary Item

Code:

Device	Prompt
Desktop	Input1
Mobile	Input1
Text	Input1

Control properties for device

Width: Pixel

Formatting: ☒ CSS-based ☐ Direct

Prompt: Prompt ☐ Hide Prompt

Value: Text Attributes...

Selected:

Keypad mode

☒ None ☐ Show ☐ Auto Popup

Properties

General | **Advanced UI**

Layout and icon

Layout: Simple

Icon: (None)

Advanced text control properties

Mask:

Maximum length: 0

Navigation and behavior

☒ None ☐ Auto Advance

☐ Auto Submit ☐ Hide OK Button

☐ Show Work Instructions ☐ Hide WI Button

☐ Skip User Control on Tab

☐ Receives Focus

☐ Allow multiple selection

☐ Show calendar

Position

☐ Absolute Position

Offset Alignment

Horizontal: 0 Left

Vertical: 0 Top

Field	Description
User Interface Control	The User Interface Control you wish to display on the screen. A sample of the UI control is displayed in the Layout Editor. The available User Interface Controls include the following: ▶ Text ▶ Long Text ▶ Masked Text

This User Interface Control is most commonly used to mask password input in runtime. To ensure that the input value is also masked in DELMIA Apriso logs, Job Executor, and Job Scheduler, the name of the input must include the word "password".

- ▶ Drop-down
- ▶ Combo Box
- ▶ Check Box
- ▶ Button
- ▶ Radio Button
- ▶ Date/Time Picker
- ▶ Date Picker
- ▶ Time Picker
- ▶ File Picker

By default, uploading files is disabled. To enable uploading, edit the AllowedUploadedFileExtensions key in central configuration: set it to "*" to accept all file types, set it to a list of specific file types separated by semicolons to accept only the listed types, or leave it empty to block all file types.

- ▶ Selection List
- ▶ Spinner

When a Button or a Selection List User Input is set to read-only (Input Values Editor, Advanced tab) and the onClick event is defined in the Attributes pop-up window, the action will be triggered even if control is disabled (default HTML link behavior). In such case onClick action needs to contain additional IF statement which determines if control is disabled or not:

```
if(!$(this).closest('table').hasClass('aspNetDisabled')).
```

Input Values...	For more information, see Input Values Editor below.
Allow external input	Selecting this check box will expose the Input as an external Input of the DFC. External Inputs can be used to pass values to the DFC when using it as sub-DFC or when invoking it from Machine Integrator/Job Scheduler/XML Manager. When this check box is selected, the External Input Name field is required. This option is disabled when the DFC Interface functionality is enabled. This option is deprecated. Use DFC Interface instead.
External input name	The name of the External Input. Used only when the Allow external input check box is selected.
Dictionary Item	▶  – Adds Dictionary Item (written in the text box) to the dictionary and links it to the Input. ▶  – Opens a Dictionary Items suggestion lookup window which is a list of existing Dictionary Items that the user may choose from. When the user

enters a part of the Dictionary Item name, the system suggests a list of matching entries from the database. The chosen Dictionary Item is linked to the Input.

When you duplicate a DFC (to a new revision or a new entity), links to Dictionary Items are copied too.

- ▶  – Unlinks the Dictionary Item.
- ▶  – Opens the Dictionary Translations screen in the context of linked Dictionary Item. For more information on this screen, refer to the [Dictionary Translations topic in the Dictionary Help](#).

The prompts associated with the Function Inputs that are displayed respectively on the following devices:

- ▶ Desktop – the prompt string (text) to be used with this Input as rendered on a desktop browser
- ▶ Mobile – the prompt string (text) to be used with this Input as rendered on a mobile browser
- ▶ Text – the prompt string (text) to be used with this Input as rendered on a text client device

Mobile and Text platforms are no longer supported.

Control properties for device (Desktop and Mobile)

Width – the size of the Input (not available for the Check Box, Radio Button, and File Picker Controls). Text longer than the width that has been set will be cut.

Hide Prompt check box – if selected, the prompt will not be displayed.

Attributes button – opens a pop-up [window](#) for the configuration of additional HTML attributes.

Formatting

- ▶ Direct – allows the user to define the fonts, colors, and alignment of the User Interface control:
 - ▷ Prompt – the formatting that applies to the desktop prompt string
 - ▷ Value – the formatting that applies to the value field on a desktop
 - ▷ Selected – the formatting that applies to the selected value of a button or selection list on the desktop,
- ▶ CSS-based—allows the user to specify a CSS class (by selecting an item from the drop-down list or typing its name) or multiple classes (separated by spaces) to be used for the following Input elements:
 - ▷ Prompt
 - ▷ Value
 - ▷ Selected Value for Button or Selection List

Classes used are based on the default theme. Using multiple classes is beneficial when there is a need to combine certain properties. For example, when text Inputs (being Values) are to be centered rather than left-aligned, in addition to the default “Prompt” class you should type “AlignCenter.”

Dassault Systèmes recommends combining classes over substituting default ones (default classes will be always set for Input prompt even in CSS class is not specified) – unless you know what you are doing! The functionality of certain controls depend on them having specific class names.

In the case of the Input Controls in Layout Editor, it is possible to assign a CSS class to a container (an HTML object directly hosting an [Input/Output](#) control) in the Value style field with the syntax `Container.ProperCSSClass` and using the classes "AlignCenter," "AlignLeft," "AlignRight."

Keypad mode (Desktop only) – enables a pop-up keyboard to be used on a touch screen or with a mouse. The list of valid keypad modes is as follows:

- ▶ None – does not allow pop-ups
- ▶ Show – allows pop-ups with user intervention
- ▶ Auto Popup – automatically renders pop-ups without user intervention

When the Input type is numeric, the system displays the **numeric** pad. Otherwise it displays the **alphanumeric** pad.


The configuration file of the keypad is `virtualKeyboard.js` *and it is* placed in Apriso\Scripts folder on the Web Server. The default keypad language displayed when the keypad is invoked is the language defined in the DELMIA Apriso Portal for the user currently logged in. The `virtualKeyboard.js` script contains language definitions for the keypad and allows adding additional languages.

Control properties for device (Text)

Characters – enables the defining of the length of the Input field

Breaks – enables the defining of the number of new lines after the user control

Advanced UI Tab



Field	Description
Layout and icon	Layout – there are 3 types of layouts: ▶ Simple ▶ Tabular ▶ Horizontal Icon – displayed to the immediate left of the Input prompt on Desktop and Mobile devices. Available icons include: ▶ Information ▶ Question ▶ Warning ▶ Error
Advanced text control properties	These options are available when the Text User Interface Control has been chosen: ▶ Mask – the user can specify the Function Input masking, which validates the entered value using the <code>RegularExpressionValidator.ValidationExpression</code> Property (see Microsoft Docs articles for details) for the controls Text, Long Text, and Spinner (e.g., <code>\d{5}</code> means 5 digits) (see <i>Regular Expression Language - Quick Reference</i> at Microsoft Docs for details) ▶ Maximum Length
Navigation and behavior	Used to control navigation from one Function Input to the next: ▶ None – no navigation ▶ Auto Advance – automatically advances to the next User Input (the Maximum Length option should be set together with this option) ▶ Auto Submit – automatically submits the page after entering the value The Auto Submit functionality may not work correctly on some "old" types of mobile devices. For more information, refer to the comments in <code>autoadvance_mobile.js</code>.

	▶ Hide OK Button ▶ Show Work Instructions – the Show Work Instructions button makes it possible to re-open the Work Instructions pop-up once it has closed (this option is only available for the Button and Selection List User Interface Control) ▶ Use this option if you plan to create your own UI element to trigger the Work Instructions pop-up – simply add the <i>ShowWIPop()</i> attribute to any User Input button (use the Attribute button on the User Input Properties pane) ▶ Hide WI Button – if selected, the Show Work Instructions button will not be displayed during runtime ▶ Skip User Control on Tab ▶ Receives Focus – this should be set for only one control ▶ Allow multiple selection – for Buttons and Selection Lists ▶ Show calendar – for Date Picker
Position	If the Absolute Position check box is selected, the user is able to change the position of the control in the Layout Editor. The user specifies the offset (in pixels) and the alignment of the control.

Input Values Editor

General Tab

User Input Values Editor

General | Advanced

☒ Show Initial Value
☐ User must enter non-blank value (required input)

Default Value

☐ None
☒ Constant
☐ Session Variable
☐ Previous Function Output
☐ System Parameter

Initial Value

☐ None
☒ Constant
☐ Session Variable
☐ Previous Function Output
☐ System Parameter

Input Value List

☐ None
☒ Static List
☐ Database Query
☐ Session Variable
☐ Previous Function Output
☐ System Parameter

Add Remove

No.	Value	Dictionary Item	Desktop Label
1	Employees	Employees	
2	Facility	Facility	Facility
3	Ext		


Repeat layout: ☒ Flow ☐ Table
Repeat direction: ☒ Horizontal ☐ Vertical

Cell spacing: 0
Cell padding: 0
Repeat columns: 0

OK Cancel Help

Field	Description
Show Initial Value	If this check box is selected, the initial value will be shown.
User must enter non-blank value (required input)	If this check box is selected, the user must enter the value.
Default Value	The value that will be used by the system in case an empty value has been entered. It is possible to choose the source of this parameter: None, Constant, Session Variable, Previous Function Output, or System Parameter. With the Combo Box and Drop-down User Input Controls, the Default Value should be set to a different value than the ones that are available.
Initial Value	The value that will be shown upon entering the screen. It is possible to choose the source of this parameter: None, Constant, Session Variable, Previous Function Output, or System Parameter.
Input Value List	The list of values that can be chosen from during runtime. The list can be specified statically, retrieved by the database query, or taken from previous Function Outputs, Session Variables, or System Parameters. ► For a Static List: It is possible to take advantage of the Quick Command functionality by setting the Quick Command No. field (for details, see the KeyboardMapping section of the Central Configuration Documentation). You can add the Dictionary Item (or link it from the existing ones) using buttons in Dictionary Item column (see the Dictionary section). ► For a Database Query: ► Master value – the actual value which populates the Input, which can be a column's name or an expression (e.g., "ColumnName*2") ► Display value – this is text displayed on the screen related to the Master value, and a column name or expression can be used Example: <pre>select P.PRODUCTNO, TT.MEDIUM from product p, text_translation tt where p.textid=tt.textid and languageid=1033</pre> When a Master value is set to "ProductNo" and a Display value "Medium", the displayed values will be values from Medium column. Values saved to the database will be values from ProductNo column. It is possible to pass image from Session Variable, Previous Function Output or System Parameter for Button or Selection List User Interface Control.
Repeat layout/ Repeat direction	The possibility to format button or selection list (chosen from User Interface Control).

Advanced Tab



Field	Description
Read-only	It is not possible to enter the input value in runtime, as it is a read-only field. The user can see what value has been entered, and may choose the source of this parameter: None, Constant, Session Variable, Previous Function Output, or System Parameter. The Read-only option works in combination with the Initial value option that has been set. If the Read-only option for the List Input is set and no corresponding Initial value exists, the Read-only setting will be ignored.
Minimum value	The minimum value which can be entered. The user may choose the source of this parameter: None, Constant, Session Variable, Previous Function Output, or System Parameter.
Maximum value	The maximum value which can be entered. The user may choose the source of this parameter: None, Constant, Session Variable, Previous Function Output, or System Parameter.
New item initial value	This option is used for the List of... Input Type. The user may choose the source of this parameter: None, Constant, Session Variable, Previous Function Output, or System Parameter.

Examples

Layout and Icon

Configuration

Enter the User Name: Value

Enter the Password 1: Value

Enter the Password 2: Value

OK

Layout: Simple
Icon: Information

Layout: Tabular
Icon: Warning

Layout: Horizontal
Icon: Warning

Function Navigation | Layout Editor

Properties

General | Advanced UI

Layout and icon

Layout: Simple

Icon: Information

Advanced text control properties

Mask:

Maximum length: 0

Navigation and behavior

☒ None

☐ Auto Advance

☐ Auto Submit ☐ Hide OK Button

☐ Show Work Instructions ☐ Hide WI Button

☐ Skip User Control on Tab

☐ Receives Focus

☐ Allow multiple selection

☐ Show calendar

Position

☐ Absolute Position

Offset Alignment

Horizontal: 0 Left

Vertical: 0 Top

Runtime display





Enter the User Name:

Enter the Password 1:



Enter the Password 2:


OK

Mask

Configuration	Runtime display
 	 

Auto Advance

Configuration	Runtime display
 Enter the User Name: Text Output Value Enter the Password 1: Value Enter the Password 2: Value OK Function Navigation Layout Editor	After entering 5 characters (set in the Maximum length option), it automatically focuses on the next control:  Enter the User Name: abcde Enter the Password 1: Enter the Password 2: OK



Properties
General Advanced UI



Layout and icon
Layout Simple
Icon (None)

Advanced text control properties
Mask
Maximum length 5

Navigation and behavior
☒ None
☒ Auto Advance
☐ Auto Submit ☐ Hide OK Button
☐ Show Work Instructions ☐ Hide WI Button
☐ Skip User Control on Tab
☐ Receives Focus
☐ Allow multiple selection
☐ Show calendar

Position
☐ Absolute Position
Offset Alignment
Horizontal 0 Left
Vertical 0 Top

Hide OK Button

Configuration	Runtime display
 The Configuration window displays the 'Enter the Password:' text control. The 'Value' property is highlighted with a red box and labeled 'User Input'. Below it, the Properties window is shown with the 'Auto Submit' radio button selected and the 'Hide OK Button' checkbox checked.	 The Runtime display window shows the 'Enter the Password:' text control with a yellow input field.

Show Work Instructions

Configuration

Product Action:

Add Update OK Cancel

OK Show Work Instructions

Function Navigation Layout Editor

Properties

General Advanced UI

Layout and icon

Layout Simple

Icon (None)

Advanced text control properties

Mask

Maximum length 0

Navigation and behavior

☐ None

☐ Auto Advance

☐ Auto Submit ☐ Hide OK Button

☒ Show Work Instructions ☐ Hide WI Button

☐ Skip User Control on Tab

☐ Receives Focus

☐ Allow multiple selection

☐ Show calendar

Position

☐ Absolute Position

Offset Alignment

Horizontal 0 Left

Vertical 0 Top

Runtime display

Product Action:

Add Update OK Cancel

OK Show Work Instructions

5 / 14 44.3% Tools Sign Comm

Configuration is loaded in Figure 1.

Test Client and Test Client instances running on the dedicated (one or more) Windows Server (this configuration is shown in Figure 2).

On the client PC (Test Client is not necessary) - this configuration can be used for both.

Figure 1: Test Client & Test Client running on Windows Server

Figure 2: Test Client running on dedicated server

Each Test Client process connects to the IT service (the host address is set in the Test Client, see configuration file in the ITSP product).

Product Action:

Add Update OK Cancel

OK

Function Navigation Layout Editor

Properties

General Advanced UI

Layout and icon

Layout Simple

Icon (None)

Advanced text control properties

Mask

Maximum length 0

Navigation and behavior

☐ None

☐ Auto Advance

☐ Auto Submit ☐ Hide OK Button

☒ Show Work Instructions ☒ Hide WI Button

☐ Skip User Control on Tab

☐ Receives Focus

☐ Allow multiple selection

☐ Show calendar

Position

☐ Absolute Position

Offset Alignment

Horizontal 0 Left

Vertical 0 Top

Product Action:

Add Update OK Cancel

OK

Test Client (also called Test bridge) can run in many configurations. The most popular are:

- Test Service and Test Client instances running on the Platform Application Server (this configuration is shown in Figure 1).
- Test Service and Test Client instances running on the dedicated (one or more) Windows Server (this configuration is shown in Figure 2).



on the client PC (Test service is not necessary) – this configuration can be used for both.

Figure 1: Test Service & Test Client running on Platform App Server



Figure 2: Test Service running on dedicated servers


Each Test Client process connects to the TS service (the host address is set in the Test Client, also checking the old HTTP protocol).

Skip User Control on Tab

Configuration	Runtime display
 The configuration window shows the 'Advanced UI' tab. The 'Skip User Control on Tab' option is checked and highlighted with a red box. A red callout points to this option with the text: 'User Input with Skip User Control on Tab option set'.	The screen after launching the DFC (the focus on the first control is always skipped using the Tab key):  The runtime display shows a form with three input fields: 'Enter the User Name:', 'Enter the Password 1:', and 'Enter the Password 2:'. The 'Enter the Password 1:' field is highlighted in yellow, indicating it has focus.

Receives Focus

Configuration	Runtime display
 The configuration window shows the 'Advanced UI' tab. The 'Receives Focus' option is checked and highlighted with a red box. A red callout points to this option with the text: 'User Control with Receives focus option set'.	The screen after launching the DFC:  The runtime display shows a form with three input fields: 'Enter the User Name:', 'Enter the Password 1:', and 'Enter the Password 2:'. The 'Enter the Password 1:' field is highlighted in yellow, indicating it has focus.



Allow multiple selection

Configuration

Product Action:
Add Product Remove Product Update Product Find Product

General Action:
OK Cancel

Function Navigation Layout Editor

Runtime display

Product Action:
Add Product Remove Product Update Product Find Product

General Action:
OK Cancel

Possibility to select all buttons

Properties

General Advanced UI

Layout and icon
Layout Simple
Icon (None)


Advanced text control properties
Mask
Maximum length 0

Navigation and behavior
☒ None
☐ Auto Advance
☒ Auto Submit ☒ Hide OK Button
☐ Show Work Instructions ☐ Hide WI Button
☐ Skip User Control on Tab
☐ Receives Focus
☒ Allow multiple selection
☐ Show calendar

Position
☐ Absolute Position
Offset Alignment
Horizontal 0 Left
Vertical 0 Top

Show calendar

Configuration



Choose a date:
1900/01/01

OK

User Control of Date Picker type

Function Navigation | Layout Editor

Properties

General | Advanced UI


Layout and icon
Layout: Simple
Icon: (None)

Advanced text control properties
Mask:
Maximum length: 0

Navigation and behavior
☒ None
☐ Auto Advance
☐ Auto Submit ☐ Hide OK Button
☐ Show Work Instructions ☐ Hide WI Button
☐ Skip User Control on Tab
☐ Receives Focus
☐ Allow multiple selection
☒ Show calendar

Position
☐ Absolute Position
Offset: Horizontal: 0, Vertical: 0
Alignment: Left, Top


Runtime display



Choose a date:
1/1/1900

OK

Show Calendar option not selected



Choose a date:
1/1/1900

January 1900

Sun	Mon	Tue	Wed	Thu	Fri	Sat
	1	2	3	4	5	6
7	8	9	10	11	12	13
14	15	16	17	18	19	20
21	22	23	24	25	26	27
28	29	30	31			

4/6/2012

Show Calendar option set