


Layout Controls

The Layout Editor makes it possible to change the layout of the user controls. The Layout Controls for grids and Sub-DFCs can be found in the [Toolbox](#). In the design area, the user can change the order of the controls and place them within the grids.

Grid (Deprecated) Properties

Step Grid Layout Control is deprecated. Rewrite the UI to use the [Grid Business Control](#).



Field	Type of Value
Layout	Enumerate: Simple, Tabular, Horizontal.
Size Limit Type	Enumerate: None, Rows, Columns. Only for Layout Horizontal or Tabular. The restriction on the number of rows or columns to display before the screen attempts to wrap the Inputs or Outputs. ▶ Limit Rows ▶ Limit Columns
Size Limit	Integer (only when the Size Limit Type is something other than None).
Width	The width of the grid. Decimal/Integer with units. Only for Layout Tabular. Can be empty.
Height	The height of the grid style. Decimal/Integer with units. Only for Layout Tabular. Can be empty.
CSS class	The user may specify a single CSS class (by selecting an item from the drop-down list or typing its name), or type multiple classes (separated by spaces) to be used for a

	Step Grid. Classes will be used based on a default theme. Using multiple classes is beneficial when there is a need to combine certain properties, e.g., to force centered alignment for all Grid values or add class AlignCenter to the existing TabularGridLayout class. You can control the alignment of individual columns (prompts and values) by adding alignment classes to the User Inputs/Outputs or by combining the two. It is also possible to assign the CSS class to a container (an HTML object directly hosting the Grid control) with the syntax <code>Container.ProperCSSClass</code>. The user may choose <code>Container.AlignCenter</code>, <code>Container.AlignLeft</code>, and <code>Container.AlignRight</code> classes to align content properly. In the case of a Simple Layout, only Desktop devices support these CSS classes. A <code>NoWrapPromptGrid</code> CSS class is available in the Default and Classic Apriso themes. Process Authors can specify this class in the tabular grid layout to prevent text from being wrapped. If all grid prompts are to be affected by the no-wrap requirement, the CSS style sheet used can be manually updated to include the correct property (<code>white-space:nowrap</code>) in the Prompt class of the desired grid class. A <code>NoWrap</code> CSS class is available in mobile stylesheets (Default and Classic). The class can be used on top of the default ones to control if prompts and other text elements are to be split into several lines if no space is available to display them. Please note that CSS knowledge is required to perform any changes to the CSS files.
Absolute Position	When selected, the user can change the position of the grid. The user specifies the offset (in pixels) and offset direction (Alignment field). The user may also drag-and-drop the elements while holding the Ctrl key (this check box will then be automatically selected). The default selection of this check box may be configured in Options.

The user can add all of the controls (except for the grid) available in the Toolbox in the Layout Editor to the grid.

A control is moved out of the grid when Absolute Position is enabled in the control's Properties pane.

Sub-DFCs Properties

For more information about the Sub-DFCs Properties tool pane, see [Sub-DFC Function](#).

Double-clicking on the Sub-DFCs inside the Layout Editor opens this DFC only if the revision is set. Otherwise, no action is performed.

Examples

Layout

Configuration

Runtime display

Layout: Tabular

Choose the next action:
Text Output.

Step Grid1

Product Options			General Options	
Add Product	Delete Product	Update Product	OK	Cancel

Function Navigation | Layout Editor

Properties

General

Name
Step Grid1

Layout
Tabular

Size Limit Type
(None)

Size Limit
0

Width
Pixel

Height
Pixel

CSS class
TabularGridLayout

☐ Absolute Position

Offset
Horizontal 0
Vertical 0

Alignment
Left
Top

Choose the next action:

Product Options			General Options	
Add Product	Delete Product	Update Product	OK	Cancel

Layout: Simple

The screenshot displays the 'Layout Editor' window. At the top, a dialog titled 'Choose the next action:' is open, showing 'Text Output.' and 'Step Grid1'. It contains two sections: 'Product Options' with buttons 'Add Product', 'Delete Product', and 'Update Product'; and 'General Options' with 'OK' and 'Cancel' buttons. Red callouts labeled 'Button Control' point to the 'Add Product' and 'Update Product' buttons. Below the dialog, the 'Properties' panel is visible, showing the 'General' tab. The 'Layout' dropdown is set to 'Simple'. Other properties include 'Size Limit Type' (None), 'Size Limit' (0), 'Width' and 'Height' (both 0 pixels), 'CSS class' (VerticalGridLayout), and 'Absolute Position' (unchecked). The 'Offset' and 'Alignment' settings are also shown.

Choose the next action:
Text Output.
Step Grid1

Product Options
Add Product Delete Product Update Product

General Options
OK Cancel

Button Control Button Control

Function Navigation Layout Editor

Properties
General

Name
Step Grid1

Layout
Simple

Size Limit Type
(None)

Size Limit
0

Width
Pixel

Height
Pixel

CSS class
VerticalGridLayout

☐ Absolute Position

Offset Alignment
Horizontal 0 Left
Vertical 0 Top

Layout: Horizontal

The screenshot displays the ProcessBuilder interface. At the top, a dialog titled "Choose the next action:" is shown, containing a "Text Output" section and a "Step Grid1" section. The "Step Grid1" section is divided into two panels: "Product Options" and "General Options". The "Product Options" panel contains three buttons: "Add Product", "Delete Product", and "Update Product". The "General Options" panel contains two buttons: "OK" and "Cancel". Red callouts labeled "Button Control" point to the "Delete Product" and "OK" buttons. Below the dialog, the "Properties" window is open, showing the "General" tab. The "Layout" property is set to "Horizontal", which is highlighted with a red box. Other properties include "Size Limit Type" (None), "Size Limit" (0), "Width" (Pixel), "Height" (Pixel), "CSS class" (HorizontalGridLayout), and "Absolute Position" (unchecked). The "Offset" and "Alignment" properties are also visible, with "Horizontal" offset set to 0 and "Left" alignment, and "Vertical" offset set to 0 and "Top" alignment.

Size Limit Type

Configuration	Runtime Display
Layout: Horizontal Size Limit Type: Limit Columns Size Limit: 1	

The screenshot displays the Delmia ApriSO interface, specifically the 'Layout Editor' tab. The main workspace shows a 'Step Grid1' with a 'Choose the next action:' dialog box overlaid. The dialog has two sections: 'Product Options' with buttons 'Add Product', 'Delete Product', and 'Update Product'; and 'General Options' with buttons 'OK' and 'Cancel'. Red callout boxes point to the 'Delete Product' and 'Update Product' buttons, labeling them as 'Column in the Step Grid'.

Below the dialog, the 'Properties' window is open, showing the 'General' tab. The 'Name' is 'Step Grid1'. The 'Layout' is set to 'Horizontal'. The 'Size Limit Type' is 'Limit Columns'. The 'Size Limit' is set to '1'. The 'Width' and 'Height' are set to 'Pixel'. The 'CSS class' is 'HorizontalGridLayout'. The 'Absolute Position' checkbox is unchecked. The 'Offset' is set to '0' for both 'Horizontal' and 'Vertical', and the 'Alignment' is set to 'Left' for 'Horizontal' and 'Top' for 'Vertical'.

On the right side of the interface, there is a separate 'Choose the next action:' dialog box. It has two sections: 'Product Options' with buttons 'Add Product', 'Delete Product', and 'Update Product'; and 'General Options' with buttons 'OK' and 'Cancel'.