

Screen Flows Usage

In the HTML Layout Editor, a `$View` object is available. This is a representation of a [Screen Flows View](#).

You can use the `$view` object only in the HTML tab (in the `<script>` tag).

These examples present the following usage scenarios that are supported in the [Screen Flows server and client modes](#):

- ▶ [Accessing HTML Elements Representing a Current View](#)
- ▶ [Submitting a Current View](#)
- ▶ [Executing a Script after View is loaded](#)
- ▶ [Executing a Script before View is unloaded](#)

The following scenario is supported only in the Screen Flows Client Mode

- ▶ [Preventing Leaving the Page with Unsaved Changes](#)

Accessing HTML Elements Representing the Current View



This scenario returns an HTML element that represents the current rendering context (the main DFC container of the current View).

```
$View.node: HTMLElement;
```

Submitting the Current View

This scenario submits the current View. If there is an Action Output from a DFC of the View, it is executed.



```
$View.submit(): void;
```

Function Navigation	HTML Layout Editor	Runtime
	HTML Tab  HTML Layout Editor Code	The SampleAction will be executed after clicking the button.

Executing a Script After the View Is Loaded

This scenario enables executing a callback when the View is loaded and added to a document object model (DOM). A callback is invoked on the `onViewLoaded` event of the View (client mode) or the "DOM content ready" event of the HTML document (server mode).


```
$View.onLoaded(func: () => void): void;
```

Function Navigation	HTML Layout Editor	Runtime
	HTML Tab  HTML Layout Editor Code	The alert will be displayed when the View is loaded.

Executing a Script Before the View Is Unloaded

This scenario enables executing a callback before the View is removed. The callback is invoked on the `onViewsUnloading` event of the View (client mode) or before the Screen is submitted (server mode).

```
$View.onUnloading(func: () => void): void;
```

Function Navigation	HTML Layout Editor	Runtime
	HTML Tab  HTML Layout Editor Code	The alert will be displayed before the View is unloaded.

It is also possible to verify if a View is being unloaded by checking the property `isUnloading` on a View object.

```
$View.isUnloading: boolean;
```

This value indicates if a View is being unloaded. It can be used to stop an execution of AJAX callbacks.


Preventing Leaving the Page with Unsaved Changes

It is supported only in the Screen Flows Client Mode.

Screen Flows functionality does not track any changes (interaction) on a View automatically. In some circumstances, there may be a need to inform the user that the action he wants to perform may discard some data he already provided. In such situations, Process Author may configure the View to notify the Screen Flows manager that data was provided setting the `hasChanges` variable as below:

```
$View.hasChanges=true
```

When a different View tries to submit the Screen, the warning message will be displayed.

Function Navigation	HTML Layout Editor	Runtime
	HTML Tab <pre>1 <!-- Here you can layout standard UI elements using HTML and write your own HTML based screen. --> 2 Press F1 for help. --> 3 <!-- Tag selection: Ctrl+Shift+ArrowUp/ArrowDown or Ctrl+Shift+MouseButton --> 4 <!-- Snippets: Ctrl+Shift+Space or in it bind tr trc fil attr key adv foc ... + Tab --> 5 6 <input type="text" onchange="\$View.hasChanges=true"/></pre> HTML Layout Editor Code	The pop-up informing the user about possibility of losing changes will be displayed. Only one dialog is shown no matter how many Views are configured with this functionality.