Writing an OS in Rust Philipp Oppermann's blog

« All Posts

Heap Allocation

Jun 26, 2019

This post adds support for heap allocation to our kernel. First, it gives an introduction to dynamic memory and shows how the borrow checker prevents common allocation errors. It then implements the basic allocation interface of Rust, creates a heap memory region, and sets up an allocator crate. At the end of this post all the allocation and collection types of the built-in alloc crate will be available to our kernel.

This blog is openly developed on GitHub. If you have any problems or questions, please open an issue there. You can also leave comments at the bottom. The complete source code for this post can be found in the post-10 branch.


▶ Table of Contents

Local and Static Variables

We currently use two types of variables in our kernel: local variables and static variables. Local variables are stored on the call stack and are only valid until the surrounding function returns. Static variables are stored at a fixed memory location and always live for the complete lifetime of the program.


Local Variables

Local variables are stored on the call stack, which is a stack data structure that supports push and pop operations. On each function entry, the parameters, the return address, and the local variables of the called function are pushed by the compiler:



The above example shows the call stack after an outer function called an inner function. We see that the call stack contains the local variables of outer first. On the inner call, the parameter 1 and the return address for the function were pushed. Then control was transferred to inner, which pushed its local variables.

After the inner function returns, its part of the call stack is popped again and only the local variables of outer remain:



```
fn outer() {
   let x = 1;
   let y = inner(x);
}
```

We see that the local variables of inner only live until the function returns. The Rust compiler enforces these lifetimes and throws an error when we use a value too long, for example when we try to return a reference to a local variable:


```
fn inner(i: usize) -> &'static u32 {
    let z = [1, 2, 3];
    &z[i]
}
```

(run the example on the playground)

While returning a reference makes no sense in this example, there are cases where we want a variable to live longer than the function. We already saw such a case in our kernel when we tried to load an interrupt descriptor table and had to use a static variable to extend the lifetime.

Static Variables

Static variables are stored at a fixed memory location separate from the stack. This memory location is assigned at compile time by the linker and encoded in the executable. Statics live for the complete runtime of the program, so they have the 'static lifetime and can always be referenced from local variables:



When the inner function returns in the above example, it's part of the call stack is destroyed. The static variables live in a separate memory range that is never destroyed, so the &Z[1] reference is still valid after the return.

Apart from the 'static lifetime, static variables also have the useful property that their location is known at compile time, so that no reference is needed for accessing it. We utilized that property for our println macro: By using a static Writer internally there is no &mut Writer reference needed to invoke the macro, which is very useful in exception handlers where we don't have access to any additional variables.

However, this property of static variables brings a crucial drawback: They are read-only by default. Rust enforces this because a data race would occur if e.g. two threads modify a static variable at the same time. The only way to modify a static variable is to encapsulate it in a Mutex type, which ensures that only a single &mut reference exists at any point in time. We already used a Mutex for our static VGA buffer Writer.

Dynamic Memory


Local and static variables are already very powerful together and enable most use cases. However, we saw that they both have their limitations:

- Local variables only live until the end of the surrounding function or block. This is because they live on the call stack and are destroyed after the surrounding function returns.
- Static variables always live for the complete runtime of the program, so there is no way to
 reclaim and reuse their memory when they're no longer needed. Also, they have unclear
 ownership semantics and are accessible from all functions, so they need to be protected by
 a Mutex when we want to modify them.

Another limitation of local and static variables is that they have a fixed size. So they can't store a collection that dynamically grows when more elements are added. (There are proposals for unsized rvalues in Rust that would allow dynamically sized local variables, but they only work in some specific cases.)


To circumvent these drawbacks, programming languages often support a third memory region for storing variables called the **heap**. The heap supports *dynamic memory allocation* at runtime through two functions called allocate and deallocate. It works in the following way: The allocate function returns a free chunk of memory of the specified size that can be used to store a variable. This variable then lives until it is freed by calling the deallocate function with a reference to the variable.

Let's go through an example:



Here the inner function uses heap memory instead of static variables for storing z. It first allocates a memory block of the required size, which returns a *mut u32 raw pointer. It then uses the ptr::write method to write the array [1,2,3] to it. In the last step, it uses the offset function to calculate a pointer to the i th element and then returns it. (Note that we omitted some required casts and unsafe blocks in this example function for brevity.)

The allocated memory lives until it is explicitly freed through a call to deallocate. Thus, the returned pointer is still valid even after inner returned and its part of the call stack was destroyed. The advantage of using heap memory compared to static memory is that the memory can be reused after it is freed, which we do through the deallocate call in outer. After that call, the situation looks like this:



We see that the z[1] slot is free again and can be reused for the next allocate call. However, we also see that z[0] and z[2] are never freed because we never deallocate them. Such a bug is called a *memory leak* and often the cause of excessive memory consumption of programs (just imagine what happens when we call inner repeatedly in a loop). This might seem bad, but there are much more dangerous types of bugs that can happen with dynamic allocation.

Common Errors

Apart from memory leaks, which are unfortunate but don't make the program vulnerable to attackers, there are two common types of bugs with more severe consequences:

- When we accidentally continue to use a variable after calling deallocate on it, we have a so-called **use-after-free** vulnerability. Such a bug causes undefined behavior and can often be exploited by attackers to execute arbitrary code.
- When we accidentally free a variable twice, we have a **double-free** vulnerability. This is problematic because it might free a different allocation that was allocated in the same spot after the first deallocate call. Thus, it can lead to an use-after-free vulnerability again.

These types of vulnerabilities are commonly known, so one might expect that people learned how to avoid them by now. But no, such vulnerabilities are still regularly found, for example this recent use-after-free vulnerability in Linux that allowed arbitrary code execution. This shows that even the best programmers are not always able to correctly handle dynamic memory in complex projects.

To avoid these issues, many languages such as Java or Python manage dynamic memory automatically using a technique called *garbage collection*. The idea is that the programmer never invokes deallocate manually. Instead, the program is regularly paused and scanned for

unused heap variables, which are then automatically deallocated. Thus, the above vulnerabilities can never occur. The drawbacks are the performance overhead of the regular scan and the probably long pause times.

Rust takes a different approach to the problem: It uses a concept called *ownership* that is able to check the correctness of dynamic memory operations at compile time. Thus no garbage collection is needed to avoid the mentioned vulnerabilities, which means that there is no performance overhead. Another advantage of this approach is that the programmer still has finegrained control over the use of dynamic memory, just like with C or C++.

Allocations in Rust

Instead of letting the programmer manually call allocate and deallocate, the Rust standard library provides abstraction types that call these functions implicitly. The most important type is <code>Box</code>, which is an abstraction for a heap-allocated value. It provides a <code>Box::new</code> constructor function that takes a value, calls allocate with the size of the value, and then moves the value to the newly allocated slot on the heap. To free the heap memory again, the <code>Box</code> type implements the <code>Drop</code> trait to call deallocate when it goes out of scope:

```
{
    let z = Box::new([1,2,3]);
    [...]
} // z goes out of scope and `deallocate` is called
```

This pattern has the strange name *resource acquisition is initialization* (or *RAII* for short). It originated in C++, where it is used to implement a similar abstraction type called std::unique ptr.

Such a type alone does not suffice to prevent all use-after-free bugs since programmers can still hold on to references after the Box goes out of scope and the corresponding heap memory slot is deallocated:

```
let x = {
    let z = Box::new([1,2,3]);
    &z[1]
}; // z goes out of scope and `deallocate` is called
println!("{}", x);
```

This is where Rust's ownership comes in. It assigns an abstract lifetime to each reference, which is the scope in which the reference is valid. In the above example, the $\, x \,$ reference is taken from the $\, z \,$ array, so it becomes invalid after $\, z \,$ goes out of scope. When you run the above example on the playground you see that the Rust compiler indeed throws an error:

The terminology can be a bit confusing at first. Taking a reference to a value is called *borrowing* the value since it's similar to a borrow in real life: You have temporary access to an object but need to return it sometime and you must not destroy it. By checking that all borrows end before an object is destroyed, the Rust compiler can guarantee that no use-after-free situation can occur.

Rust's ownership system goes even further and does not only prevent use-after-free bugs, but provides complete *memory safety* like garbage collected languages like Java or Python do. Additionally, it guarantees *thread safety* and is thus even safer than those languages in multi-threaded code. And most importantly, all these checks happen at compile time, so there is no runtime overhead compared to hand written memory management in C.

Use Cases

We now know the basics of dynamic memory allocation in Rust, but when should we use it? We've come really far with our kernel without dynamic memory allocation, so why do we need it now?

First, dynamic memory allocation always comes with a bit of performance overhead, since we need to find a free slot on the heap for every allocation. For this reason local variables are generally preferable, especially in performance sensitive kernel code. However, there are cases where dynamic memory allocation is the best choice.

As a basic rule, dynamic memory is required for variables that have a dynamic lifetime or a variable size. The most important type with a dynamic lifetime is <code>Rc</code>, which counts the references to its wrapped value and deallocates it after all references went out of scope. Examples for types with a variable size are <code>Vec</code>, <code>String</code>, and other collection types that dynamically grow when more elements are added. These types work by allocating a larger amount of memory when they become full, copying all elements over, and then deallocating the old allocation.

For our kernel we will mostly need the collection types, for example for storing a list of active tasks when implementing multitasking in future posts.

The Allocator Interface

The first step in implementing a heap allocator is to add a dependency on the built-in alloc crate. Like the core crate, it is a subset of the standard library that additionally contains the allocation and collection types. To add the dependency on alloc, we add the following to our lib.rs:

```
// in src/lib.rs
extern crate alloc;
```

Contrary to normal dependencies, we don't need to modify the <code>Cargo.toml</code> . The reason is that the <code>alloc</code> crate ships with the Rust compiler as part of the standard library, so the compiler already knows about the crate. By adding this <code>extern</code> crate statement, we specify that the compiler should try to include it. (Historically, all dependencies needed an <code>extern</code> crate statement, which is now optional).

Since we are compiling for a custom target, we can't use the precompiled version of alloc that is shipped with the Rust installation. Instead, we have to tell cargo to recompile the crate from source. We can do that, by adding it to the unstable.build-std array in our

```
.cargo/config.toml file:
```

```
# in .cargo/config.toml
[unstable]
build-std = ["core", "compiler_builtins", "alloc"]
```

Now the compiler will recompile and include the alloc crate in our kernel.

The reason that the alloc crate is disabled by default in #[no_std] crates is that it has additional requirements. We can see these requirements as errors when we try to compile our project now:

```
error: no global memory allocator found but one is required; link to std or add
    #[global_allocator] to a static item that implements the GlobalAlloc trait.
error: `#[alloc_error_handler]` function required, but not found
```

The first error occurs because the alloc crate requires an heap allocator, which is an object that provides the allocate and deallocate functions. In Rust, heap allocators are described by the GlobalAlloc trait, which is mentioned in the error message. To set the heap allocator for the crate, the #[global_allocator] attribute must be applied to a static variable that implements the GlobalAlloc trait.

The second error occurs because calls to allocate can fail, most commonly when there is no more memory available. Our program must be able to react to this case, which is what the # [alloc_error_handler] function is for.

We will describe these traits and attributes in detail in the following sections.

The GlobalAlloc Trait

The GlobalAlloc trait defines the functions that a heap allocator must provide. The trait is special because it is almost never used directly by the programmer. Instead, the compiler will automatically insert the appropriate calls to the trait methods when using the allocation and collection types of alloc.

Since we will need to implement the trait for all our allocator types, it is worth taking a closer look at its declaration:

```
pub unsafe trait GlobalAlloc {
    unsafe fn alloc(&self, layout: Layout) -> *mut u8;
    unsafe fn dealloc(&self, ptr: *mut u8, layout: Layout);

unsafe fn alloc_zeroed(&self, layout: Layout) -> *mut u8 { ... }
    unsafe fn realloc(
        &self,
        ptr: *mut u8,
        layout: Layout,
        new_size: usize
    ) -> *mut u8 { ... }
}
```

It defines the two required methods alloc and dealloc, which correspond to the allocate and deallocate functions we used in our examples:

- The alloc method takes a Layout instance as argument, which describes the desired size and alignment that the allocated memory should have. It returns a raw pointer to the first byte of the allocated memory block. Instead of an explicit error value, the alloc method returns a null pointer to signal an allocation error. This is a bit non-idiomatic, but it has the advantage that wrapping existing system allocators is easy, since they use the same convention.
- The dealloc method is the counterpart and responsible for freeing a memory block again. It receives two arguments, the pointer returned by alloc and the Layout that was used for the allocation.

The trait additionally defines the two methods alloc_zeroed and realloc with default implementations:

- The alloc_zeroed method is equivalent to calling alloc and then setting the allocated memory block to zero, which is exactly what the provided default implementation does. An allocator implementation can override the default implementations with a more efficient custom implementation if possible.
- The realloc method allows to grow or shrink an allocation. The default implementation allocates a new memory block with the desired size and copies over all the content from the previous allocation. Again, an allocator implementation can probably provide a more efficient implementation of this method, for example by growing/shrinking the allocation inplace if possible.

Unsafety

One thing to notice is that both the trait itself and all trait methods are declared as unsafe:

- The reason for declaring the trait as unsafe is that the programmer must guarantee that
 the trait implementation for an allocator type is correct. For example, the alloc method
 must never return a memory block that is already used somewhere else because this would
 cause undefined behavior.
- Similarly, the reason that the methods are unsafe is that the caller must ensure various
 invariants when calling the methods, for example that the Layout passed to alloc
 specifies a non-zero size. This is not really relevant in practice since the methods are
 normally called directly by the compiler, which ensures that the requirements are met.

A DummyAllocator

Now that we know what an allocator type should provide, we can create a simple dummy allocator. For that we create a new allocator module:

```
// in src/lib.rs
pub mod allocator;
```

Our dummy allocator does the absolute minimum to implement the trait and always return an error when alloc is called. It looks like this:

```
// in src/allocator.rs

use alloc::alloc::{GlobalAlloc, Layout};
use core::ptr::null_mut;

pub struct Dummy;

unsafe impl GlobalAlloc for Dummy {
    unsafe fn alloc(&self, _layout: Layout) -> *mut u8 {
        null_mut()
```

```
unsafe fn dealloc(&self, _ptr: *mut u8, _layout: Layout) {
   panic!("dealloc should be never called")
}
```

The struct does not need any fields, so we create it as a zero sized type. As mentioned above, we always return the null pointer from alloc, which corresponds to an allocation error. Since the allocator never returns any memory, a call to dealloc should never occur. For this reason we simply panic in the dealloc method. The alloc_zeroed and realloc methods have default implementations, so we don't need to provide implementations for them.

We now have a simple allocator, but we still have to tell the Rust compiler that it should use this allocator. This is where the #[global allocator] attribute comes in.

The #[global allocator] Attribute

The #[global_allocator] attribute tells the Rust compiler which allocator instance it should use as the global heap allocator. The attribute is only applicable to a static that implements the GlobalAlloc trait. Let's register an instance of our Dummy allocator as the global allocator:

```
// in src/allocator.rs
#[global_allocator]
static ALLOCATOR: Dummy = Dummy;
```

Since the Dummy allocator is a zero sized type, we don't need to specify any fields in the initialization expression.

When we now try to compile it, the first error should be gone. Let's fix the remaining second error:

```
error: `#[alloc error handler]` function required, but not found
```

The #[alloc error handler] Attribute

As we learned when discussing the GlobalAlloc trait, the alloc function can signal an allocation error by returning a null pointer. The question is: how should the Rust runtime react to such an allocation failure? This is where the #[alloc_error_handler] attribute comes in. It specifies a function that is called when an allocation error occurs, similar to how our panic handler is called when a panic occurs.

Let's add such a function to fix the compilation error:

```
// in src/lib.rs

#![feature(alloc_error_handler)] // at the top of the file

#[alloc_error_handler]
fn alloc_error_handler(layout: alloc::alloc::Layout) -> ! {
    panic!("allocation error: {:?}", layout)
}
```

The alloc_error_handler function is still unstable, so we need a feature gate to enable it. The function receives a single argument: the Layout instance that was passed to alloc when the allocation failure occurred. There's nothing we can do to resolve the failure, so we just panic with a message that contains the Layout instance.

With this function, the compilation errors should be fixed. Now we can use the allocation and collection types of alloc, for example we can use a Box to allocate a value on the heap:

```
// in src/main.rs

extern crate alloc;

use alloc::boxed::Box;

fn kernel_main(boot_info: &'static BootInfo) -> ! {
    // [...] print "Hello World!", call `init`, create `mapper` and `frame_allocator`
    let x = Box::new(41);

    // [...] call `test_main` in test mode

    println!("It did not crash!");
    blog_os::hlt_loop();
}
```

Note that we need to specify the extern crate alloc statement in our main.rs too. This is required because the lib.rs and main.rs part are treated as separate crates. However, we don't need to create another #[global_allocator] static because the global allocator applies to all crates in the project. In fact, specifying an additional allocator in another crate would be an error.

When we run the above code, we see that our alloc_error_handler function is called:

```
• QEMU ● ® ⊗

Hello World!
panicked at 'allocation error: Layout { size_: 4, align_: 4 }', src/lib.rs:89:5
```

The error handler is called because the Box::new function implicitly calls the alloc function of the global allocator. Our dummy allocator always returns a null pointer, so every allocation fails. To fix this we need to create an allocator that actually returns usable memory.

Creating a Kernel Heap

Before we can create a proper allocator, we first need to create a heap memory region from which the allocator can allocate memory. To do this, we need to define a virtual memory range for the heap region and then map this region to physical frames. See the "Introduction To Paging" post for an overview of virtual memory and page tables.

The first step is to define a virtual memory region for the heap. We can choose any virtual address range that we like, as long as it is not already used for a different memory region. Let's define it as the memory starting at address 0x_4444_4444_0000 so that we can easily recognize a heap pointer later:

```
// in src/allocator.rs
pub const HEAP_START: usize = 0x_4444_4444_0000;
pub const HEAP_SIZE: usize = 100 * 1024; // 100 KiB
```

We set the heap size to 100 KiB for now. If we need more space in the future, we can simply increase it.

If we tried to use this heap region now, a page fault would occur since the virtual memory region is not mapped to physical memory yet. To resolve this, we create an <code>init_heap</code> function that maps the heap pages using the <code>Mapper API</code> that we introduced in the "Paging Implementation" post:

```
// in src/allocator.rs
use x86 64::{
    structures::paging::{
        mapper::MapToError, FrameAllocator, Mapper, Page, PageTableFlags, Size4KiB,
    },
    VirtAddr,
};
pub fn init heap(
    mapper: &mut impl Mapper<Size4KiB>,
    frame allocator: &mut impl FrameAllocator<Size4KiB>,
) -> Result<(), MapToError<Size4KiB>> {
    let page range = {
        let heap start = VirtAddr::new(HEAP START as u64);
        let heap end = heap start + HEAP SIZE - 1u64;
        let heap start page = Page::containing address(heap start);
        let heap end page = Page::containing_address(heap_end);
        Page::range inclusive(heap start page, heap end page)
    };
    for page in page_range {
        let frame = frame allocator
            .allocate frame()
            .ok or(MapToError::FrameAllocationFailed)?;
        let flags = PageTableFlags::PRESENT | PageTableFlags::WRITABLE;
        unsafe {
            mapper.map_to(page, frame, flags, frame_allocator)?.flush()
        };
    }
    0k(())
}
```

The function takes mutable references to a Mapper and a FrameAllocator instance, both limited to 4KiB pages by using Size4KiB as generic parameter. The return value of the function is a Result with the unit type () as success variant and a MapToError as error variant, which is the error type returned by the Mapper::map_to method. Reusing the error type makes sense here because the map_to method is the main source of errors in this function.

The implementation can be broken down into two parts:

- Creating the page range: To create a range of the pages that we want to map, we convert the HEAP_START pointer to a VirtAddr type. Then we calculate the heap end address from it by adding the HEAP_SIZE. We want an inclusive bound (the address of the last byte of the heap), so we subtract 1. Next, we convert the addresses into Page types using the containing_address function. Finally, we create a page range from the start and end pages using the Page::range inclusive function.
- Mapping the pages: The second step is to map all pages of the page range we just created. For that we iterate over the pages in that range using a for loop. For each page, we do the following:
 - We allocate a physical frame that the page should be mapped to using the
 FrameAllocator::allocate_frame method. This method returns None when there
 are no more frames left. We deal with that case by mapping it to a
 MapToError::FrameAllocationFailed error through the Option::ok_or method
 and then apply the question mark operator to return early in the case of an error.
 - We set the required PRESENT flag and the WRITABLE flag for the page. With these flags both read and write accesses are allowed, which makes sense for heap memory.
 - We use the Mapper::map_to method for creating the mapping in the active page table. The method can fail, therefore we use the question mark operator again to forward the error to the caller. On success, the method returns a MapperFlush instance that we can use to update the *translation lookaside buffer* using the flush method.

The final step is to call this function from our kernel main:

```
// in src/main.rs

fn kernel_main(boot_info: &'static BootInfo) -> ! {
    use blog_os::allocator; // new import
    use blog_os::memory::{self, BootInfoFrameAllocator};

    println!("Hello World{}", "!");
    blog_os::init();

    let phys_mem_offset = VirtAddr::new(boot_info.physical_memory_offset);
    let mut mapper = unsafe { memory::init(phys_mem_offset) };
    let mut frame_allocator = unsafe {
        BootInfoFrameAllocator::init(&boot_info.memory_map)
    };

    // new
    allocator::init_heap(&mut mapper, &mut frame_allocator)
```

```
.expect("heap initialization failed");
let x = Box::new(41);

// [...] call `test_main` in test mode

println!("It did not crash!");
blog_os::hlt_loop();
}
```

We show the full function for context here. The only new lines are the <code>blog_os::allocator</code> import and the call to <code>allocator::init_heap</code> function. In case the <code>init_heap</code> function returns an error, we panic using the <code>Result::expect</code> method since there is currently no sensible way for us to handle this error.

We now have a mapped heap memory region that is ready to be used. The Box::new call still uses our old Dummy allocator, so you will still see the "out of memory" error when you run it. Let's fix this by using a proper allocator.

Using an Allocator Crate

Since implementing an allocator is somewhat complex, we start by using an external allocator crate. We will learn how to implement our own allocator in the next post.

A simple allocator crate for no_std applications is the linked_list_allocator crate. It's name comes from the fact that it uses a linked list data structure to keep track of deallocated memory regions. See the next post for a more detailed explanation of this approach.

To use the crate, we first need to add a dependency on it in our Cargo.toml:

```
# in Cargo.toml
[dependencies]
linked list allocator = "0.9.0"
```

Then we can replace our dummy allocator with the allocator provided by the crate:

```
// in src/allocator.rs

use linked_list_allocator::LockedHeap;

#[global_allocator]
static ALLOCATOR: LockedHeap = LockedHeap::empty();
```

The struct is named LockedHeap because it uses the spinning_top::Spinlock type for synchronization. This is required because multiple threads could access the ALLOCATOR static at

the same time. As always when using a spinlock or a mutex, we need to be careful to not accidentally cause a deadlock. This means that we shouldn't perform any allocations in interrupt handlers, since they can run at an arbitrary time and might interrupt an in-progress allocation.

Setting the LockedHeap as global allocator is not enough. The reason is that we use the empty constructor function, which creates an allocator without any backing memory. Like our dummy allocator, it always returns an error on alloc. To fix this, we need to initialize the allocator after creating the heap:

```
// in src/allocator.rs

pub fn init_heap(
    mapper: &mut impl Mapper<Size4KiB>,
    frame_allocator: &mut impl FrameAllocator<Size4KiB>,
) -> Result<(), MapToError<Size4KiB>> {
    // [...] map all heap pages to physical frames

    // new
    unsafe {
        ALLOCATOR.lock().init(HEAP_START, HEAP_SIZE);
    }

    Ok(())
}
```

We use the lock method on the inner spinlock of the LockedHeap type to get an exclusive reference to the wrapped Heap instance, on which we then call the init method with the heap bounds as arguments. It is important that we initialize the heap *after* mapping the heap pages, since the init function already tries to write to the heap memory.

After initializing the heap, we can now use all allocation and collection types of the built-in alloc crate without error:

```
// in src/main.rs

use alloc::{boxed::Box, vec, vec::Vec, rc::Rc};

fn kernel_main(boot_info: &'static BootInfo) -> ! {
    // [...] initialize interrupts, mapper, frame_allocator, heap

    // allocate a number on the heap
    let heap_value = Box::new(41);
    println!("heap_value at {:p}", heap_value);

    // create a dynamically sized vector
    let mut vec = Vec::new();
    for i in 0..500 {
        vec.push(i):
```


```
println!("vec at {:p}", vec.as_slice());

// create a reference counted vector -> will be freed when count reaches 0
let reference_counted = Rc::new(vec![1, 2, 3]);
let cloned_reference = reference_counted.clone();
println!("current reference count is {}", Rc::strong_count(&cloned_reference));
core::mem::drop(reference_counted);
println!("reference count is {} now", Rc::strong_count(&cloned_reference));

// [...] call `test_main` in test context
println!("It did not crash!");
blog_os::hlt_loop();
}
```

This code example shows some uses of the Box, Vec, and Rc types. For the Box and Vec types we print the underlying heap pointers using the <code>{:p}</code> formatting specifier. For showcasing Rc, we create a reference counted heap value and use the <code>Rc::strong_count</code> function to print the current reference count, before and after dropping an instance (using <code>core::mem::drop</code>).

When we run it, we see the following:



As expected, we see that the Box and Vec values live on the heap, as indicated by the pointer starting with the 0x 4444 4444 * prefix. The reference counted value also behaves as

expected, with the reference count being 2 after the clone call, and 1 again after one of the instances was dropped.

The reason that the vector starts at offset 0x800 is not that the boxed value is 0x800 bytes large, but the reallocations that occur when the vector needs to increase its capacity. For example, when the vector's capacity is 32 and we try to add the next element, the vector allocates a new backing array with capacity 64 behind the scenes and copies all elements over. Then it frees the old allocation.

Of course there are many more allocation and collection types in the alloc crate that we can now all use in our kernel, including:

- the thread-safe reference counted pointer Arc
- the owned string type String and the format! macro
- LinkedList
- the growable ring buffer VecDeque
- the BinaryHeap priority queue
- BTreeMap and BTreeSet

These types will become very useful when we want to implement thread lists, scheduling queues, or support for async/await.

Adding a Test

To ensure that we don't accidentally break our new allocation code, we should add an integration test for it. We start by creating a new tests/heap_allocation.rs file with the following content:

```
// in tests/heap_allocation.rs

#![no_std]
#![no_main]
#![feature(custom_test_frameworks)]
#![test_runner(blog_os::test_runner)]
#![reexport_test_harness_main = "test_main"]

extern crate alloc;

use bootloader::{entry_point, BootInfo};
use core::panic::PanicInfo;
entry_point!(main);

fn main(boot_info: &'static BootInfo) -> ! {
    unimplemented!();
}

#[panic_handler]
```

```
fn panic(info: &PanicInfo) -> ! {
    blog_os::test_panic_handler(info)
}
```

We reuse the test_runner and test_panic_handler functions from our lib.rs . Since we want to test allocations, we enable the alloc crate through the extern crate alloc statement. For more information about the test boilerplate check out the *Testing* post.

The implementation of the main function looks like this:

```
// in tests/heap allocation.rs
fn main(boot info: &'static BootInfo) -> ! {
    use blog os::allocator;
    use blog os::memory::{self, BootInfoFrameAllocator};
    use x86_64::VirtAddr;
    blog os::init();
    let phys mem offset = VirtAddr::new(boot info.physical memory offset);
    let mut mapper = unsafe { memory::init(phys mem offset) };
    let mut frame_allocator = unsafe {
        BootInfoFrameAllocator::init(&boot info.memory map)
    };
    allocator::init heap(&mut mapper, &mut frame allocator)
        .expect("heap initialization failed");
    test main();
    loop {}
}
```

It is very similar to the kernel_main function in our main.rs, with the differences that we don't invoke println, don't include any example allocations, and call test main unconditionally.

Now we're ready to add a few test cases. First, we add a test that performs some simple allocations using Box and checks the allocated values, to ensure that basic allocations work:

```
// in tests/heap_allocation.rs
use alloc::boxed::Box;

#[test_case]
fn simple_allocation() {
    let heap_value_1 = Box::new(41);
    let heap_value_2 = Box::new(13);
    assert_eq!(*heap_value_1, 41);
    assert_eq!(*heap_value_2, 13);
}
```

Most importantly, this test verifies that no allocation error occurs.

Next, we iteratively build a large vector, to test both large allocations and multiple allocations (due to reallocations):

```
// in tests/heap_allocation.rs

use alloc::vec::Vec;

#[test_case]
fn large_vec() {
    let n = 1000;
    let mut vec = Vec::new();
    for i in 0..n {
        vec.push(i);
    }
    assert_eq!(vec.iter().sum::<u64>(), (n - 1) * n / 2);
}
```

We verify the sum by comparing it with the formula for the n-th partial sum. This gives us some confidence that the allocated values are all correct.

As a third test, we create ten thousand allocations after each other:

```
// in tests/heap_allocation.rs

use blog_os::allocator::HEAP_SIZE;

#[test_case]
fn many_boxes() {
    for i in 0..HEAP_SIZE {
        let x = Box::new(i);
        assert_eq!(*x, i);
    }
}
```

This test ensures that the allocator reuses freed memory for subsequent allocations since it would run out of memory otherwise. This might seem like an obvious requirement for an allocator, but there are allocator designs that don't do this. An example is the bump allocator design that will be explained in the next post.

Let's run our new integration test:

```
> cargo test --test heap_allocation
[...]
Running 3 tests
simple_allocation... [ok]
large_vec... [ok]
many boxes... [ok]
```

All three tests succeeded! You can also invoke cargo test (without --test argument) to run all unit and integration tests.

Summary

This post gave an introduction to dynamic memory and explained why and where it is needed. We saw how Rust's borrow checker prevents common vulnerabilities and learned how Rust's allocation API works.

After creating a minimal implementation of Rust's allocator interface using a dummy allocator, we created a proper heap memory region for our kernel. For that we defined a virtual address range for the heap and then mapped all pages of that range to physical frames using the Mapper and FrameAllocator from the previous post.

Finally, we added a dependency on the $linked_list_allocator$ crate to add a proper allocator to our kernel. With this allocator, we were able to use Box, Vec, and other allocation and collection types from the alloc crate.

What's next?

While we already added heap allocation support in this post, we left most of the work to the linked_list_allocator crate. The next post will show in detail how an allocator can be implemented from scratch. It will present multiple possible allocator designs, shows how to implement simple versions of them, and explain their advantages and drawbacks.

Support Me

Creating and maintaining this blog and the associated libraries is a lot of work, but I really enjoy doing it. By supporting me, you allow me to invest more time in new content, new features, and continuous maintenance.

The best way to support me is to *sponsor me on GitHub*, since they don't charge any fees. If you prefer other platforms, I also have *Patreon* and *Donorbox* accounts. The latter is the most flexible as it supports multiple currencies and one-time contributions.

Thank you!


« Paging Implementation

Allocator Designs »

0 reactions



0 comments



Instead of authenticating the giscus application, you can also comment directly on the on GitHub. Just click the "X comments" link at the top — or the date of any comment — to go to the GitHub discussion.

About Me

I'm a Rust freelancer with a master's degree in computer science. I love systems programming, open source software, and new challenges.

If you want to work with me, reach out on LinkedIn or write me at job@phil-opp.com.

© 2021. All rights reserved. Contact