

Red Hat Enterprise Linux 8 Installing Identity Management

Getting started using Identity Management

Last Updated: 2021-09-07

Red Hat Enterprise Linux 8 Installing Identity Management

Getting started using Identity Management

Legal Notice

Copyright © 2021 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

http://creativecommons.org/licenses/by-sa/3.0/

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java [®] is a registered trademark of Oracle and/or its affiliates.

XFS [®] is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL ® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack [®] Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

This documentation collection provides instructions on how to install Identity Management on Red Hat Enterprise Linux 8 (RHEL) and how to upgrade to it from RHEL 7.

Table of Contents

MAKING OPEN SOURCE MORE INCLUSIVE	. 7
PROVIDING FEEDBACK ON RED HAT DOCUMENTATION	. 8
PART I. INSTALLING IDENTITY MANAGEMENT	. 9
CHAPTER 1. PREPARING THE SYSTEM FOR IDM SERVER INSTALLATION	10
1.1. AUTHORIZATION REQUIREMENTS WHEN INSTALLING AN IDM SERVER	10
1.2. HARDWARE RECOMMENDATIONS	10
1.3. CUSTOM CONFIGURATION REQUIREMENTS FOR IDM	10
1.3.1. IPv6 requirements in IdM	10
1.3.2. Support for encryption types in IdM	10
1.3.3. FIPS compliance	12
1.4. TIME SERVICE REQUIREMENTS FOR IDM	13
1.4.1. How IdM uses chronyd for synchronization	13
1.4.2. List of NTP configuration options for IdM installation commands	13
1.4.3. Ensuring IdM can reference your NTP time server	14
1.4.4. Additional resources	14
1.5. HOST NAME AND DNS REQUIREMENTS FOR IDM	14
1.6. PORT REQUIREMENTS FOR IDM	18
Opening the required ports	18
1.7. INSTALLING PACKAGES REQUIRED FOR AN IDM SERVER	19
CHAPTER 2. INSTALLING AN IDM SERVER: WITH INTEGRATED DNS, WITH AN INTEGRATED CA AS THE	
ROOT CA	22
2.1. INTERACTIVE INSTALLATION	22
2.2. NON-INTERACTIVE INSTALLATION	24
CHAPTER 3. INSTALLING AN IDM SERVER: WITH INTEGRATED DNS, WITH AN EXTERNAL CA AS THE RO	
CA	26
3.1. INTERACTIVE INSTALLATION	26
3.2. TROUBLESHOOTING: EXTERNAL CA INSTALLATION FAILS	29
What this means:	29
To fix the problem:	30
CHAPTER 4. INSTALLING AN IDM SERVER: WITH INTEGRATED DNS, WITHOUT A CA	31
4.1. CERTIFICATES REQUIRED TO INSTALL AN IDM SERVER WITHOUT A CA	31
4.2. INTERACTIVE INSTALLATION	32
CHARTER E INICTALLING AN IRM CERVER, WITHOUT INTECRATER DNC WITH AN INTECRATER CA AC	
CHAPTER 5. INSTALLING AN IDM SERVER: WITHOUT INTEGRATED DNS, WITH AN INTEGRATED CA AS ROOT CA	
5.1. INTERACTIVE INSTALLATION	36
5.2. NON-INTERACTIVE INSTALLATION	37
5.3. IDM DNS RECORDS FOR EXTERNAL DNS SYSTEMS	38
5.5. IDM DNS RECORDS FOR EXTERINAL DNS STSTEMS	30
CHAPTER 6. INSTALLING AN IDM SERVER: WITHOUT INTEGRATED DNS, WITH AN EXTERNAL CA AS TH	
ROOT CA	Ε
	40
6.1. INTERACTIVE INSTALLATION	40 40
6.2. NON-INTERACTIVE INSTALLATION	40
	40 40
6.2. NON-INTERACTIVE INSTALLATION	40 40 42
6.2. NON-INTERACTIVE INSTALLATION 6.3. IDM DNS RECORDS FOR EXTERNAL DNS SYSTEMS	40 40 42 44
6.2. NON-INTERACTIVE INSTALLATION 6.3. IDM DNS RECORDS FOR EXTERNAL DNS SYSTEMS CHAPTER 7. TROUBLESHOOTING IDM SERVER INSTALLATION	40 42 44 46

7.3. REMOVING A PARTIAL IDM SERVER INSTALLATION 7.4. ADDITIONAL RESOURCES	48 49
CHAPTER 8. UNINSTALLING AN IDM SERVER	50
CHAPTER 9. RENAMING AN IDM SERVER	51
CHAPTER 10. PREPARING THE SYSTEM FOR IDM CLIENT INSTALLATION 10.1. DNS REQUIREMENTS FOR IDM CLIENTS Additional resources 10.2. PORT REQUIREMENTS FOR IDM CLIENTS 10.3. IPV6 REQUIREMENTS FOR IDM CLIENTS 10.4. PACKAGES REQUIRED TO INSTALL AN IDM CLIENT 10.4.1. Installing ipa-client packages from the idm:client stream 10.4.2. Installing ipa-client packages from the idm:DL1 stream	52 52 52 52 52 53 53
CHAPTER 11. INSTALLING AN IDM CLIENT: BASIC SCENARIO 11.1. PREREQUISITES 11.2. INSTALLING A CLIENT BY USING USER CREDENTIALS: INTERACTIVE INSTALLATION 11.3. INSTALLING A CLIENT BY USING A ONE-TIME PASSWORD: INTERACTIVE INSTALLATION 11.4. INSTALLING A CLIENT: NON-INTERACTIVE INSTALLATION 11.5. REMOVING PRE-IDM CONFIGURATION AFTER INSTALLING A CLIENT 11.6. TESTING AN IDM CLIENT 11.7. CONNECTIONS PERFORMED DURING AN IDM CLIENT INSTALLATION 11.8. IDM CLIENT'S COMMUNICATIONS WITH THE SERVER DURING POST-INSTALLATION DEPLOYMENT 11.8.1. SSSD communication patterns 11.8.2. Certmonger communication patterns	55 55 57 58 60 60 61 62 63
CHAPTER 12. INSTALLING AN IDM CLIENT WITH KICKSTART 12.1. INSTALLING A CLIENT WITH KICKSTART 12.2. KICKSTART FILE FOR CLIENT INSTALLATION 12.3. TESTING AN IDM CLIENT	65 65 65 66
CHAPTER 13. TROUBLESHOOTING IDM CLIENT INSTALLATION 13.1. REVIEWING IDM CLIENT INSTALLATION ERRORS 13.2. RESOLVING ISSUES IF THE CLIENT INSTALLATION FAILS TO UPDATE DNS RECORDS 13.3. RESOLVING ISSUES IF THE CLIENT INSTALLATION FAILS TO JOIN THE IDM KERBEROS REALM 13.4. ADDITIONAL RESOURCES	67 68 68 69
CHAPTER 14. RE-ENROLLING AN IDM CLIENT 14.1. CLIENT RE-ENROLLMENT IN IDM 14.1.1. What happens during client re-enrollment 14.2. RE-ENROLLING A CLIENT BY USING USER CREDENTIALS: INTERACTIVE RE-ENROLLMENT 14.3. RE-ENROLLING A CLIENT BY USING THE CLIENT KEYTAB: NON-INTERACTIVE RE-ENROLLMENT 14.4. TESTING AN IDM CLIENT	70 70 70 70 71 71
CHAPTER 15. UNINSTALLING AN IDM CLIENT 15.1. UNINSTALLING AN IDM CLIENT 15.2. UNINSTALLING AN IDM CLIENT: ADDITIONAL STEPS AFTER MULTIPLE PAST INSTALLATIONS	73 73 74
CHAPTER 16. RENAMING IDM CLIENT SYSTEMS 16.1. PREREQUISITES 16.2. UNINSTALLING AN IDM CLIENT 16.3. UNINSTALLING AN IDM CLIENT: ADDITIONAL STEPS AFTER MULTIPLE PAST INSTALLATIONS 16.4. RENAMING THE HOST SYSTEM 16.5. RE-INSTALLING AN IDM CLIENT	76 76 77 78 79 79

16.6. RE-ADDING SERVICES, RE-GENERATING CERTIFICATES, AND RE-ADDING HOST GROUPS	79
CHAPTER 17. PREPARING THE SYSTEM FOR IDM REPLICA INSTALLATION	80
17.2. METHODS FOR DISPLAYING IDM SOFTWARE VERSION	80
17.3. AUTHORIZING THE INSTALLATION OF A REPLICA ON AN IDM CLIENT	81
17.4. AUTHORIZING THE INSTALLATION OF A REPLICA ON A SYSTEM THAT IS NOT ENROLLED INTO ID	M 82
CHAPTER 18. INSTALLING AN IDM REPLICA	84
18.1. INSTALLING AN IDM REPLICA WITH INTEGRATED DNS AND A CA	84
18.2. INSTALLING AN IDM REPLICA WITH INTEGRATED DNS	85
18.3. INSTALLING AN IDM REPLICA WITH A CA	86
18.4. INSTALLING AN IDM REPLICA WITHOUT A CA	87
18.5. INSTALLING AN IDM HIDDEN REPLICA	88
18.6. TESTING AN IDM REPLICA	88
18.7. CONNECTIONS PERFORMED DURING AN IDM REPLICA INSTALLATION	89
CHAPTER 19. TROUBLESHOOTING IDM REPLICA INSTALLATION	90
19.1. REVIEWING IDM REPLICA INSTALLATION ERRORS	90
19.2. REVIEWING IDM CA INSTALLATION ERRORS	92
19.3. REMOVING A PARTIAL IDM REPLICA INSTALLATION	93
19.4. RESOLVING INVALID CREDENTIAL ERRORS	94
19.5. ADDITIONAL RESOURCES	95
CHAPTER 20. UNINSTALLING AN IDM REPLICA	96
CHAPTER 21. INSTALLING AND RUNNING THE IDM HEALTHCHECK TOOL	97
21.1. HEALTHCHECK IN IDM	97
21.1.1. Modules are Independent	97
21.1.2. Two output formats	97
21.1.3. Results	97
21.2. INSTALLING IDM HEALTHCHECK	98
21.3. RUNNING IDM HEALTHCHECK	98
21.4. ADDITIONAL RESOURCES	98
CHAPTER 22. INSTALLING AN IDENTITY MANAGEMENT SERVER USING AN ANSIBLE PLAYBOOK	100
22.1. ANSIBLE AND ITS ADVANTAGES FOR INSTALLING IDM	100
Advantages of using Ansible to install IdM	100
22.2. IDM SERVER INSTALLATION USING AN ANSIBLE PLAYBOOK	100
Overview	100
22.3. INSTALLING THE ANSIBLE-FREEIPA PACKAGE	101
22.4. ANSIBLE ROLES LOCATION IN THE FILE SYSTEM	101
22.5. DEPLOYING AN IDM SERVER WITH AN INTEGRATED CA AS THE ROOT CA USING AN ANSIBLE PLAYBOOK	102
22.5.1. Setting the parameters for a deployment with an integrated CA as the root CA	102
22.5.2. Deploying an IdM server with an integrated CA as the root CA using an Ansible playbook	104
22.6. DEPLOYING AN IDM SERVER WITH AN EXTERNAL CA AS THE ROOT CA USING AN ANSIBLE	10.4
PLAYBOOK	104
22.6.1. Setting the parameters for a deployment with an external CA as the root CA	104
22.6.2. Deploying an IdM server with an external CA as the root CA using an Ansible playbook	107
CHAPTER 23. INSTALLING AN IDENTITY MANAGEMENT REPLICA USING AN ANSIBLE PLAYBOOK	108
23.1. IDM REPLICA INSTALLATION USING AN ANSIBLE PLAYBOOK	108
Overview	108

23.2. SETTING THE PARAMETERS OF THE IDM REPLICA DEPLOYMENT	108
23.2.1. Specifying the base, server and client variables for installing the IdM replica	109
23.2.2. Specifying the credentials for installing the IdM replica using an Ansible playbook	111
23.3. DEPLOYING AN IDM REPLICA USING AN ANSIBLE PLAYBOOK	112
CHAPTER 24. INSTALLING AN IDENTITY MANAGEMENT CLIENT USING AN ANSIBLE PLAYBOOK	114
24.1. IDM CLIENT INSTALLATION USING AN ANSIBLE PLAYBOOK	114
Overview	114
24.2. SETTING THE PARAMETERS OF THE IDM CLIENT DEPLOYMENT	114
24.2.1. Setting the parameters of the inventory file for the autodiscovery client installation mode	115
24.2.2. Setting the parameters of the inventory file when autodiscovery is not possible during client installat	tion
	117
24.2.3. Checking the parameters in the install-client.yml file	119
24.2.4. Authorization options for IdM client enrollment using an Ansible playbook	119
24.3. DEPLOYING AN IDM CLIENT USING AN ANSIBLE PLAYBOOK	121
24.4. TESTING AN IDENTITY MANAGEMENT CLIENT AFTER ANSIBLE INSTALLATION	122
24.5. UNINSTALLING AN IDM CLIENT USING AN ANSIBLE PLAYBOOK	122
PART II. INTEGRATING IDM AND AD	124
CHAPTER 25. INSTALLING TRUST BETWEEN IDM AND AD	125
25.1. SUPPORTED VERSIONS OF WINDOWS SERVER	125
25.2. HOW THE TRUST WORKS	126
25.3. AD ADMINISTRATION RIGHTS	126
25.4. ENSURING SUPPORT FOR COMMON ENCRYPTION TYPES IN AD AND RHEL	126
25.5. PORTS REQUIRED FOR COMMUNICATION BETWEEN IDM AND AD	127
25.6. CONFIGURING DNS AND REALM SETTINGS FOR A TRUST	130
25.6.1. Unique primary DNS domains	130
25.6.2. Configuring DNS zones in the IdM Web UI	131
25.6.3. Configuring DNS forwarding in AD	134
25.6.4. Verifying the DNS configuration	135
25.7. CONFIGURING IDM CLIENTS IN AN ACTIVE DIRECTORY DNS DOMAIN	136
25.7.1. Configuring an IdM client without Kerberos single sign-on	136
25.7.2. Requesting SSL certificates without single sign-on	137
25.7.3. Configuring an IdM client with Kerberos single sign-on	137
25.7.4. Requesting SSL certificates with single sign-on	138
25.8. SETTING UP A TRUST	138
25.8.1. Preparing the IdM server for the trust	139
25.8.2. Setting up a trust agreement using the command line	141
25.8.3. Setting up a trust agreement in the IdM Web UI	141
25.8.4. Verifying the Kerberos configuration	143
25.8.5. Verifying the trust configuration on IdM	144
25.8.6. Verifying the trust configuration on AD	145
25.8.7. Creating a trust agent	146
25.9. REMOVING THE TRUST USING THE COMMAND LINE	147
25.10. REMOVING THE TRUST USING THE IDM WEB UI	148
PART III. MIGRATING IDM FROM RHEL 7 TO RHEL 8 AND KEEPING IT UP-TO-DATE	150
CHAPTER 26. MIGRATING YOUR IDM ENVIRONMENT FROM RHEL 7 SERVERS TO RHEL 8 SERVERS	151
26.1. PREREQUISITES FOR MIGRATING IDM FROM RHEL 7 TO 8	152
26.2. INSTALLING THE RHEL 8 REPLICA	153
26.3. ASSIGNING THE CA RENEWAL SERVER ROLE TO THE RHEL 8 IDM SERVER	155
26.4. STOPPING CRL GENERATION ON A RHEL 7 IDM CA SERVER	155

26.5. STARTING CRL GENERATION ON THE NEW RHEL 8 IDM CA SERVER 26.6. STOPPING AND DECOMMISSIONING THE RHEL 7 SERVER	156 157
CHAPTER 27. UPDATING AND DOWNGRADING IDM	158
CHAPTER 28. UPGRADING AN IDM CLIENT FROM RHEL 7 TO RHEL 8	159
28.1. UPDATING THE SSSD CONFIGURATION AFTER UPGRADING TO RHEL 8	159
28.1.1. Switching from the local ID provider to the files ID provider	159
28.1.2. Removing deprecated options	160
28.1.3. Enabling wildcard matching for sudo rules	160
28.2. LIST OF SSSD FUNCTIONALITY REMOVED IN RHEL 8	161
28.3. ADDITIONAL RESOURCES	162

MAKING OPEN SOURCE MORE INCLUSIVE

Red Hat is committed to replacing problematic language in our code, documentation, and web properties. We are beginning with these four terms: master, slave, blacklist, and whitelist. Because of the enormity of this endeavor, these changes will be implemented gradually over several upcoming releases. For more details, see our CTO Chris Wright's message.

In Identity Management, planned terminology replacements include:

- block list replaces blacklist
- allow list replaces whitelist
- secondary replaces slave
- The word *master* is being replaced with more precise language, depending on the context:
 - IdM server replaces IdM master
 - CA renewal server replaces CA renewal master
 - CRL publisher server replaces CRL master
 - multi-supplier replaces multi-master

PROVIDING FEEDBACK ON RED HAT DOCUMENTATION

We appreciate your input on our documentation. Please let us know how we could make it better. To do so:

- For simple comments on specific passages:
 - 1. Make sure you are viewing the documentation in the *Multi-page HTML* format. In addition, ensure you see the **Feedback** button in the upper right corner of the document.
 - 2. Use your mouse cursor to highlight the part of text that you want to comment on.
 - 3. Click the Add Feedback pop-up that appears below the highlighted text.
 - 4. Follow the displayed instructions.
- For submitting more complex feedback, create a Bugzilla ticket:
 - 1. Go to the Bugzilla website.
 - 2. As the Component, use **Documentation**.
 - 3. Fill in the **Description** field with your suggestion for improvement. Include a link to the relevant part(s) of documentation.
 - 4. Click Submit Bug.

PART I. INSTALLING IDENTITY MANAGEMENT

CHAPTER 1. PREPARING THE SYSTEM FOR IDM SERVER INSTALLATION

The following sections list the requirements to install an Identity Management (IdM) server. Before the installation, make sure your system meets these requirements.

1.1. AUTHORIZATION REQUIREMENTS WHEN INSTALLING AN IDM SERVER

You need root privileges to install an Identity Management (IdM) server on your host.

1.2. HARDWARE RECOMMENDATIONS

RAM is the most important hardware feature to size properly. Make sure your system has enough RAM available. Typical RAM requirements are:

- For 10,000 users and 100 groups: at least 4 GB of RAM and 4 GB swap space
- For 100,000 users and 50,000 groups: at least 16 GB of RAM and 4 GB of swap space

For larger deployments, it is more effective to increase the RAM than to increase disk space because much of the data is stored in cache. In general, adding more RAM leads to better performance for larger deployments due to caching.



NOTE

A basic user entry or a simple host entry with a certificate is approximately 5–10 kB in size.

1.3. CUSTOM CONFIGURATION REQUIREMENTS FOR IDM

Install an Identity Management (IdM) server on a clean system without any custom configuration for services such as DNS, Kerberos, Apache, or Directory Server.

The IdM server installation overwrites system files to set up the IdM domain. IdM backs up the original system files to /var/lib/ipa/sysrestore/. When an IdM server is uninstalled at the end of the lifecycle, these files are restored.

1.3.1. IPv6 requirements in IdM

The IdM system must have the IPv6 protocol enabled in the kernel. If IPv6 is disabled, then the CLDAP plug-in used by the IdM services fails to initialize.



NOTE

IPv6 does not have to be enabled on the network.

1.3.2. Support for encryption types in IdM

Red Hat Enterprise Linux (RHEL) uses Version 5 of the Kerberos protocol, which supports encryption types such as Advanced Encryption Standard (AES), Camellia, and Data Encryption Standard (DES).

List of supported encryption types

While the Kerberos libraries on IdM servers and clients might support more encryption types, the IdM Kerberos Distribution Center (KDC) only supports the following encryption types:

- aes256-cts:normal
- aes256-cts:special (default)
- aes128-cts:normal
- aes128-cts:special (default)
- aes128-sha2:normal
- aes128-sha2:special
- aes256-sha2:normal
- aes256-sha2:special
- camellia128-cts-cmac:normal
- camellia128-cts-cmac:special
- camellia256-cts-cmac:normal
- camellia256-cts-cmac:special

RC4 encryption types are disabled by default

The following RC4 encryption types have been deprecated and disabled by default in RHEL 8, as they are considered less secure than the newer AES-128 and AES-256 encryption types:

- arcfour-hmac:normal
- arcfour-hmac:special

For more information on manually enabling RC4 support for compatibility with legacy Active Directory environments, see Ensuring support for common encryption types in AD and RHEL.

Support for DES and 3DES encryption has been removed

Due to security reasons, support for the DES algorithm was deprecated in RHEL 7. The recent rebase of Kerberos packages in RHEL 8.3.0 removes support for single-DES (DES) and triple-DES (3DES) encryption types from RHEL 8.



NOTE

Standard RHEL 8 IdM installations do not use DES or 3DES encryption types by default and are unaffected by the Kerberos upgrade.

If you manually configured any services or users to **only** use DES or 3DES encryption (for example, for legacy clients), you might experience service interruptions after updating to the latest Kerberos packages, such as:

• Kerberos authentication errors

- **unknown enctype** encryption errors
- KDCs with DES-encrypted Database Master Keys (K/M) fail to start

Red Hat recommends you do not use DES or 3DES encryption in your environment.



NOTE

You only need to disable DES and 3DES encryption types if you configured your environment to use them.

1.3.3. FIPS compliance

With RHEL 8.3.0 or later, you can install a new IdM server or replica on a system with the Federal Information Processing Standard (FIPS) mode enabled.

To install IdM with FIPS, first enable FIPS mode on the host, then install IdM. The IdM installation script detects if FIPS is enabled and configures IdM to only use encryption types that are compliant with FIPS 140-2:

- aes256-cts:normal
- aes256-cts:special
- aes128-cts:normal
- aes128-cts:special
- aes128-sha2:normal
- aes128-sha2:special
- aes256-sha2:normal
- aes256-sha2:special

For an IdM environment to be FIPS-compliant, **all** IdM servers and replicas must have FIPS mode enabled.

Support for cross-forest trust with FIPS mode enabled

To establish a cross-forest trust with an Active Directory (AD) domain while FIPS mode is enabled, you must meet the following requirements:

- IdM servers are on RHEL 8.4.0 or later.
- You must authenticate with an AD administrative account when setting up a trust. You cannot establish a trust using a shared secret while FIPS mode is enabled.



IMPORTANT

RADIUS authentication is not FIPS compliant. Do not install IdM on a server with FIPS mode enabled if you require RADIUS authentication.

Additional Resources

- To enable FIPS mode in the RHEL operating system, see Switching the system to FIPS mode in the Security Hardening guide.
- For more details on FIPS 140-2, see the Security Requirements for Cryptographic Modules on the National Institute of Standards and Technology (NIST) web site.

1.4. TIME SERVICE REQUIREMENTS FOR IDM

The following sections discuss using **chronyd** to keep your IdM hosts in sync with a central time source:

- How IdM uses **chronyd** for synchronization
- List of NTP configuration options for IdM installation commands
- Ensuring IdM can reference your NTP time server

1.4.1. How IdM uses chronyd for synchronization

Kerberos, the underlying authentication mechanism in IdM, uses time stamps as part of its protocol. Kerberos authentication fails if the system time of an IdM client differs by more than five minutes from the system time of the Key Distribution Center (KDC).

To ensure that IdM servers and clients stay in sync with a central time source, IdM installation scripts automatically configure **chronyd** Network Time Protocol (NTP) client software.

If you do not pass any NTP options to the IdM installation command, the installer searches for _ntp._udp DNS service (SRV) records that point to the NTP server in your network and configures chrony with that IP address. If you do not have any _ntp._udp SRV records, chronyd uses the configuration shipped with the chrony package.



NOTE

Because **ntpd** has been deprecated in favor of **chronyd** in RHEL 8, IdM servers are no longer configured as Network Time Protocol (NTP) servers and are only configured as NTP clients. The RHEL 7 **NTP Server** IdM server role has also been deprecated in RHEL 8.

1.4.2. List of NTP configuration options for IdM installation commands

You can specify the following options with any of the IdM installation commands (**ipa-server-install**, **ipa-replica-install**, **ipa-client-install**) to configure **chronyd** client software during setup.

Table 1.1. List of NTP configuration options for IdM installation commands

Option	Behavior
ntp-server	Use it to specify one NTP server. You can use it multiple times to specify multiple servers.
ntp-pool	Use it to specify a pool of multiple NTP servers resolved as one hostname.
-N,no-ntp	Do not configure, start, or enable chronyd .

1.4.3. Ensuring IdM can reference your NTP time server

This procedure verifies you have the necessary configurations in place for IdM to be able to synchronize with your Network Time Protocol (NTP) time server.

Prerequisites

• You have configured an NTP time server in your environment. In this example, the hostname of the previously configured time server is **ntpserver.example.com**.

Procedure

1. Perform a DNS service (SRV) record search for NTP servers in your environment.

```
[user@server ~]$ dig +short -t SRV _ntp._udp.example.com 0 100 123 ntpserver.example.com.
```

2. If the previous **dig** search does not return your time server, add a __**ntp._udp** SRV record that points to your time server on port **123**. This process depends on your DNS solution.

Verification steps

 Verify that DNS returns an entry for your time server on port 123 when you perform a search for _ntp._udp SRV records.

```
[user@server ~]$ dig +short -t SRV _ntp._udp.example.com 0 100 123 ntpserver.example.com.
```

1.4.4. Additional resources

- Implementation of NTP
- Using the Chrony suite to configure NTP

1.5. HOST NAME AND DNS REQUIREMENTS FOR IDM

This section lists the host name and DNS requirements for server and replica systems. It also shows how to verify that the systems meet the requirements.

The requirements in this section apply to all Identity Management (IdM) servers, those with integrated DNS and those without integrated DNS.



WARNING

DNS records are vital for nearly all IdM domain functions, including running LDAP directory services, Kerberos, and Active Directory integration. Be extremely cautious and ensure that:

- You have a tested and functional DNS service available
- The service is properly configured

This requirement applies to IdM servers with and without integrated DNS.

Verify the server host name

The host name must be a fully qualified domain name, such as **server.idm.example.com**. The fully qualified domain name must meet the following conditions:

- It is a valid DNS name, which means only numbers, alphabetic characters, and hyphens (-) are allowed. Other characters, such as underscores (_), in the host name cause DNS failures.
- It is all lower-case. No capital letters are allowed.
- It does not resolve to the loopback address. It must resolve to the system's public IP address, not to **127.0.0.1**.

To verify the host name, use the **hostname** utility on the system where you want to install:

hostname

server.idm.example.com

The output of **hostname** must not be **localhost** or **localhost**6.

Verify the forward and reverse DNS configuration

- 1. Obtain the IP address of the server.
 - a. The **ip addr show** command displays both the IPv4 and IPv6 addresses. In the following example, the relevant IPv6 address is **2001:DB8::1111** because its scope is global:

```
[root@server ~]# ip addr show
...
2: eth0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast state UP group default qlen 1000
link/ether 00:1a:4a:10:4e:33 brd ff:ff:ff:ff
inet 192.0.2.1/24 brd 192.0.2.255 scope global dynamic eth0
valid_lft 106694sec preferred_lft 106694sec
inet6 2001:DB8::1111/32 scope global dynamic
valid_lft 2591521sec preferred_lft 604321sec
inet6 fe80::56ee:75ff:fe2b:def6/64 scope link
valid_lft forever preferred_lft forever
...
```

- 2. Verify the forward DNS configuration using the **dig** utility.
 - a. Run the command **dig +short** *server.idm.example.com* **A**. The returned IPv4 address must match the IP address returned by **ip addr show**:

[root@server ~]# dig +short server.idm.example.com A 192.0.2.1

b. Run the command **dig +short** *server.idm.example.com* **AAAA**. If it returns an address, it must match the IPv6 address returned by **ip addr show**:

[root@server ~]# dig +short server.idm.example.com AAAA 2001:DB8::1111



NOTE

If **dig** does not return any output for the AAAA record, it does not indicate incorrect configuration. No output only means that no IPv6 address is configured in DNS for the system. If you do not intend to use the IPv6 protocol in your network, you can proceed with the installation in this situation.

3. Verify the reverse DNS configuration (PTR records). Use the **dig** utility and add the IP address.

If the commands below display a different host name or no host name, the reverse DNS configuration is incorrect.

a. Run the command **dig +short -x** *IPv4_address*. The output must display the server host name. For example:

[root@server ~]# dig +short -x 192.0.2.1 server.idm.example.com

b. If the command **dig +short -x** server.idm.example.com **AAAA** in the previous step returned an IPv6 address, use **dig** to query the IPv6 address too. The output must display the server host name. For example:

[root@server ~]# dig +short -x 2001:DB8::1111 server.idm.example.com



NOTE

If dig +short server.idm.example.com AAAA in the previous step did not display any IPv6 address, querying the AAAA record does not output anything. In this case, this is normal behavior and does not indicate incorrect configuration.



WARNING

If a reverse DNS (PTR record) search returns multiple host names, **httpd** and other software associated with IdM may show unpredictable behavior. Red Hat strongly recommends configuring only one PTR record per IP.

Verify the standards-compliance of DNS forwarders (required for integrated DNS only)

Ensure that all DNS forwarders you want to use with the IdM DNS server comply with the Extension Mechanisms for DNS (EDNSO) and DNS Security Extensions (DNSSEC) standards. To do this, inspect the output of the following command for each forwarder separately:

\$ dig +dnssec @IP_address_of_the_DNS_forwarder . SOA

The expected output displayed by the command contains the following information:

• status: NOERROR

flags: ra

• EDNS flags: do

• The **RRSIG** record must be present in the **ANSWER** section

If any of these items is missing from the output, inspect the documentation for your DNS forwarder and verify that EDNSO and DNSSEC are supported and enabled. In the latest versions of the BIND server, the **dnssec-enable yes**; option must be set in the /etc/named.conf file.

Example of the expected output produced by **dig**:

```
;; ->>HEADER<<- opcode: QUERY, status: NOERROR, id: 48655
;; flags: qr rd ra ad; QUERY: 1, ANSWER: 2, AUTHORITY: 0, ADDITIONAL: 1

;; OPT PSEUDOSECTION:
; EDNS: version: 0, flags: do; udp: 4096

;; ANSWER SECTION:
. 31679 IN SOA a.root-servers.net. nstld.verisign-grs.com. 2015100701 1800 900 604800 86400
. 31679 IN RRSIG SOA 8 0 86400 20151017170000 20151007160000 62530 . GNVz7SQs [...]
```

Verify the/etc/hosts file

Verify that the /etc/hosts file fulfills one of the following conditions:

- The file does not contain an entry for the host. It only lists the IPv4 and IPv6 localhost entries for the host.
- The file contains an entry for the host and the file fulfills all the following conditions:
 - The first two entries are the IPv4 and IPv6 localhost entries.

- The next entry specifies the IdM server IPv4 address and host name.
- The **FQDN** of the IdM server comes before the short name of the IdM server.
- The IdM server host name is not part of the localhost entry.

The following is an example of a correctly configured /etc/hosts file:

127.0.0.1 localhost localhost.localdomain \
localhost4 localhost4.localdomain4
::1 localhost localhost.localdomain \
localhost6 localhost6.localdomain6
192.0.2.1 server.idm.example.com server
2001:DB8::1111 server.idm.example.com server

1.6. PORT REQUIREMENTS FOR IDM

Identity Management (IdM) uses a number of ports to communicate with its services. These ports must be open and available for incoming connections to the IdM server for IdM to work. They must not be currently used by another service or blocked by a firewall.

Table 1.2. IdM ports

Service	Ports	Protocol
HTTP/HTTPS	80, 443	ТСР
LDAP/LDAPS	389, 636	TCP
Kerberos	88, 464	TCP and UDP
DNS	53	TCP and UDP (optional)
NTP	123	UDP (optional)

In addition, ports 8080, 8443, and 749 must be free as they are used internally. Do not open these ports and instead leave them blocked by a firewall.

Table 1.3. firewalld services

Service name	For details, see:
freeipa-Idap	/usr/lib/firewalld/services/freeipa-ldap.xml
freeipa-Idaps	/usr/lib/firewalld/services/freeipa-ldaps.xml
dns	/usr/lib/firewalld/services/dns.xml

Opening the required ports

- 1. Make sure the **firewalld** service is running.
 - To find out if **firewalld** is currently running:
 - # systemctl status firewalld.service
 - To start **firewalld** and configure it to start automatically when the system boots:
 - # systemctl start firewalld.service # systemctl enable firewalld.service
- 2. Open the required ports using the **firewall-cmd** utility. Choose one of the following options:
 - a. Add the individual ports to the firewall by using the **firewall-cmd --add-port** command. For example, to open the ports in the default zone:

```
# firewall-cmd --permanent --add-port= {80/tcp,443/tcp,389/tcp,636/tcp,88/tcp,88/udp,464/tcp,464/udp,53/tcp,53/udp,123/udp}
```

- b. Add the **firewalld** services to the firewall by using the **firewall-cmd** --add-service command. For example, to open the ports in the default zone:
 - # firewall-cmd --permanent --add-service={freeipa-ldap,freeipa-ldaps,dns}

For details on using **firewall-cmd** to open ports on a system, see the **firewall-cmd**(1) man page.

- 3. Reload the **firewall-cmd** configuration to ensure that the change takes place immediately:
 - # firewall-cmd --reload

Note that reloading **firewalld** on a system in production can cause DNS connection time outs. If required, to avoid the risk of time outs and to make the changes persistent on the running system, use the **--runtime-to-permanent** option of the **firewall-cmd** command, for example:

- # firewall-cmd --runtime-to-permanent
- 4. **Optional.** To verify that the ports are available now, use the **nc**, **telnet**, or **nmap** utilities to connect to a port or run a port scan.



NOTE

Note that you also have to open network-based firewalls for both incoming and outgoing traffic.

1.7. INSTALLING PACKAGES REQUIRED FOR AN IDM SERVER

In RHEL8, the packages necessary for installing an Identity Management (IdM) server are shipped as a module. The IdM server module stream is called the **DL1** stream, and you need to enable this stream before downloading packages from this stream. The following procedure shows how to download the packages necessary for setting up the IdM environment of your choice.

Prerequisites

- You have a newly installed RHEL system.
- You have made the required repositories available:
 - If your RHEL system is not running in the cloud, you have registered your system with the Red Hat Subscription Manager (RHSM). For details, see Registration, attaching, and removing subscriptions in the Subscription Manager command line. You have also enabled the BaseOS and AppStream repositories that IdM uses:

subscription-manager repos --enable=rhel-8-for-x86_64-baseos-rpms # subscription-manager repos --enable=rhel-8-for-x86_64-appstream-rpms

For details on how to enable and disable specific repositories using RHSM, see Configuring options in Red Hat Subscription Manager.

- If your RHEL system is running in the cloud, skip the registration. The required repositories are already available via the Red Hat Update Infrastructure (RHUI).
- You have not previously enabled an IdM module stream.

Procedure

- 1. Enable the idm:DL1 stream:
 - # yum module enable idm:DL1
- 2. Switch to the RPMs delivered through the idm:DL1 stream:
 - # yum distro-sync
- 3. Choose one of the following options, depending on your IdM requirements:
 - To download the packages necessary for installing an IdM server without an integrated DNS:
 - # yum module install idm:DL1/server
 - To download the packages necessary for installing an IdM server with an integrated DNS:
 - # yum module install idm:DL1/dns
 - To download the packages necessary for installing an IdM server that has a trust agreement with Active Directory:
 - # yum module install idm:DL1/adtrust
 - To download the packages from multiple profiles, for example the adtrust and dns profiles:
 - # yum module install idm:DL1/{dns,adtrust}
 - To download the packages necessary for installing an IdM client:
 - # yum module install idm:DL1/client



IMPORTANT

When switching to a new module stream once you have already enabled a different stream and downloaded packages from it, you need to first explicitly remove all the relevant installed content and disable the current module stream before enabling the new module stream. Trying to enable a new stream without disabling the current one results in an error. For details on how to proceed, see Switching to a later stream.



WARNING

While it is possible to install packages from modules individually, be aware that if you install any package from a module that is not listed as "API" for that module, it is only going to be supported by Red Hat in the context of that module. For example, if you install **bind-dyndb-ldap** directly from the repository to use with your custom 389 Directory Server setup, any problems that you have will be ignored unless they occur for IdM, too.

CHAPTER 2. INSTALLING AN IDM SERVER: WITH INTEGRATED DNS, WITH AN INTEGRATED CA AS THE ROOT CA

Installing a new Identity Management (IdM) server with integrated DNS has the following advantages:

- You can automate much of the maintenance and DNS record management using native IdM tools. For example, DNS SRV records are automatically created during the setup, and later on are automatically updated.
- You can have a stable connection with the rest of the Internet by setting up global forwarders
 during the installation of the IdM server. Global forwarders are also useful for trusts with Active
 Directory.
- You can set up a DNS reverse zone to prevent emails from your domain to be considered spam by email servers outside of the IdM domain.

Installing IdM with integrated DNS has certain limitations:

• IdM DNS is not meant to be used as a general-purpose DNS server. Some of the advanced DNS functions are not supported.

This chapter describes how you can install a new IdM server with an integrated certificate authority (CA) as the root CA.



NOTE

The default configuration for the **ipa-server-install** command is an integrated CA as the root CA. If no CA option, for example **--external-ca** or **--ca-less** is specified, the IdM server is installed with an integrated CA.

2.1. INTERACTIVE INSTALLATION

During the interactive installation using the **ipa-server-install** utility, you are asked to supply basic configuration of the system, for example the realm, the administrator's password and the Directory Manager's password.

The **ipa-server-install** installation script creates a log file at /**var/log/ipaserver-install.log**. If the installation fails, the log can help you identify the problem.

Procedure

- 1. Run the ipa-server-install utility.
 - # ipa-server-install
- 2. The script prompts to configure an integrated DNS service. Enter yes.
 - Do you want to configure integrated DNS (BIND)? [no]: yes
- 3. The script prompts for several required settings and offers recommended default values in brackets.
 - To accept a default value, press **Enter**.

• To provide a custom value, enter the required value.

Server host name [server.example.com]: Please confirm the domain name [example.com]: Please provide a realm name [EXAMPLE.COM]:



WARNING

Plan these names carefully. You will not be able to change them after the installation is complete.

4. Enter the passwords for the Directory Server superuser (**cn=Directory Manager**) and for the Identity Management (IdM) administration system user account (**admin**).

Directory Manager password: IPA admin password:

5. The script prompts for DNS forwarders.

Do you want to configure DNS forwarders? [yes]:

- To configure DNS forwarders, enter yes, and then follow the instructions on the command line. The installation process will add the forwarder IP addresses to the /etc/named.conf file on the installed IdM server.
 - For the forwarding policy default settings, see the **--forward-policy** description in the **ipa-dns-install**(1) man page.
- If you do not want to use DNS forwarding, enter no.
 With no DNS forwarders, your environment will be isolated, and names from other DNS domains in your infrastructure will not be resolved.
- 6. The script prompts to check if any DNS reverse (PTR) records for the IP addresses associated with the server need to be configured.

Do you want to search for missing reverse zones? [yes]:

If you run the search and missing reverse zones are discovered, the script asks you whether to create the reverse zones along with the PTR records.

Do you want to create reverse zone for IP 192.0.2.1 [yes]: Please specify the reverse zone name [2.0.192.in-addr.arpa.]: Using reverse zone(s) 2.0.192.in-addr.arpa.



NOTE

Using IdM to manage reverse zones is optional. You can use an external DNS service for this purpose instead.

7. Enter **yes** to confirm the server configuration.

Continue to configure the system with these values? [no]: yes

- 8. The installation script now configures the server. Wait for the operation to complete.
- 9. After the installation script completes, update your DNS records in the following way:
 - a. Add DNS delegation from the parent domain to the IdM DNS domain. For example, if the IdM DNS domain is *idm.example.com*, add a name server (NS) record to the **example.com** parent domain.



IMPORTANT

Repeat this step each time after an IdM DNS server is installed.

b. Add an _ntp._udp service (SRV) record for your time server to your IdM DNS. The presence of the SRV record for the time server of the newly-installed IdM server in IdM DNS ensures that future replica and client installations are automatically configured to synchronize with the time server used by this primary IdM server.

2.2. NON-INTERACTIVE INSTALLATION



NOTE

The **ipa-server-install** installation script creates a log file at /**var/log/ipaserver-install.log**. If the installation fails, the log can help you identify the problem.

Procedure

- 1. Run the **ipa-server-install** utility with the options to supply all the required information. The minimum required options for non-interactive installation are:
 - --realm to provide the Kerberos realm name
 - --ds-password to provide the password for the Directory Manager (DM), the Directory Server super user
 - **--admin-password** to provide the password for **admin**, the Identity Management (IdM) administrator
 - --unattended to let the installation process select default options for the host name and domain name

To install a server with integrated DNS, add also these options:

- --setup-dns to configure integrated DNS
- **--forwarder** or **--no-forwarders**, depending on whether you want to configure DNS forwarders or not
- --auto-reverse or --no-reverse, depending on whether you want to configure automatic
 detection of the reverse DNS zones that must be created in the IdM DNS or no reverse
 zone auto-detection

For example:

ipa-server-install --realm *EXAMPLE.COM* --ds-password *DM_password* --admin-password *admin_password* --unattended --setup-dns --forwarder *192.0.2.1* --no-reverse

- 2. After the installation script completes, update your DNS records in the following way:
 - a. Add DNS delegation from the parent domain to the IdM DNS domain. For example, if the IdM DNS domain is *idm.example.com*, add a name server (NS) record to the **example.com** parent domain.



IMPORTANT

Repeat this step each time after an IdM DNS server is installed.

b. Add an _ntp._udp service (SRV) record for your time server to your IdM DNS. The presence of the SRV record for the time server of the newly-installed IdM server in IdM DNS ensures that future replica and client installations are automatically configured to synchronize with the time server used by this primary IdM server.

Additional resources

• For a complete list of options accepted by **ipa-server-install**, run the **ipa-server-install --help** command.

CHAPTER 3. INSTALLING AN IDM SERVER: WITH INTEGRATED DNS, WITH AN EXTERNAL CA AS THE ROOT CA

Installing a new Identity Management (IdM) server with integrated DNS has the following advantages:

- You can automate much of the maintenance and DNS record management using native IdM tools. For example, DNS SRV records are automatically created during the setup, and later on are automatically updated.
- You can have a stable connection with the rest of the Internet by setting up global forwarders
 during the installation of the IdM server. Global forwarders are also useful for trusts with Active
 Directory.
- You can set up a DNS reverse zone to prevent emails from your domain to be considered spam by email servers outside of the IdM domain.

Installing IdM with integrated DNS has certain limitations:

• IdM DNS is not meant to be used as a general-purpose DNS server. Some of the advanced DNS functions are not supported.

This chapter describes how you can install a new IdM server with an external certificate authority (CA) as the root CA.

3.1. INTERACTIVE INSTALLATION

During the interactive installation using the **ipa-server-install** utility, you are asked to supply basic configuration of the system, for example the realm, the administrator's password and the Directory Manager's password.

The **ipa-server-install** installation script creates a log file at /**var/log/ipaserver-install.log**. If the installation fails, the log can help you identify the problem.

This procedure describes how to install a server:

- with integrated DNS
- with an external certificate authority (CA) as the root CA

Prerequisites

- Decide on the type of the external CA you use (the **--external-ca-type** option). See the **ipa-server-install**(1) man page for details.
- Alternatively, decide on the --external-ca-profile option allowing an alternative Active Directory Certificate Services (AD CS) template to be specified. For example, to specify an AD CS installation-specific object identifier:

[root@server ~]# ipa-server-install --external-ca --external-ca-type=ms-cs --external-ca-profile=1.3.6.1.4.1.311.21.8.8950086.10656446.2706058.12775672.480128.147.7130143.44 05632:1

Procedure

1. Run the **ipa-server-install** utility with the **--external-ca** option.

ipa-server-install --external-ca

If you are using the Microsoft Certificate Services CA, use also the **--external-ca-type** option. For details, see the **ipa-server-install** (1) man page.

2. The script prompts to configure an integrated DNS service. Enter **yes** or **no**. In this procedure, we are installing a server with integrated DNS.

Do you want to configure integrated DNS (BIND)? [no]: yes



NOTE

If you want to install a server without integrated DNS, the installation script will not prompt you for DNS configuration as described in the steps below. See Chapter 5, Installing an IdM server: Without integrated DNS, with an integrated CA as the root CA for details on the steps for installing a server without DNS.

- 3. The script prompts for several required settings and offers recommended default values in brackets.
 - To accept a default value, press **Enter**.
 - To provide a custom value, enter the required value.

Server host name [server.example.com]: Please confirm the domain name [example.com]: Please provide a realm name [EXAMPLE.COM]:



WARNING

Plan these names carefully. You will not be able to change them after the installation is complete.

4. Enter the passwords for the Directory Server superuser (**cn=Directory Manager**) and for the Identity Management (IdM) administration system user account (**admin**).

Directory Manager password: IPA admin password:

5. The script prompts for DNS forwarders.

Do you want to configure DNS forwarders? [yes]:

 To configure DNS forwarders, enter yes, and then follow the instructions on the command line. The installation process will add the forwarder IP addresses to the /etc/named.conf file on the installed IdM server.

- For the forwarding policy default settings, see the **--forward-policy** description in the **ipa-dns-install**(1) man page.
- If you do not want to use DNS forwarding, enter no.
 With no DNS forwarders, your environment will be isolated, and names from other DNS domains in your infrastructure will not be resolved.
- 6. The script prompts to check if any DNS reverse (PTR) records for the IP addresses associated with the server need to be configured.

Do you want to search for missing reverse zones? [yes]:

If you run the search and missing reverse zones are discovered, the script asks you whether to create the reverse zones along with the PTR records.

Do you want to create reverse zone for IP 192.0.2.1 [yes]: Please specify the reverse zone name [2.0.192.in-addr.arpa.]: Using reverse zone(s) 2.0.192.in-addr.arpa.



NOTE

Using IdM to manage reverse zones is optional. You can use an external DNS service for this purpose instead.

- 7. Enter **yes** to confirm the server configuration.
 - Continue to configure the system with these values? [no]: yes
- 8. During the configuration of the Certificate System instance, the utility prints the location of the certificate signing request (CSR): /root/ipa.csr:

...

Configuring certificate server (pki-tomcatd): Estimated time 3 minutes 30 seconds

[1/8]: creating certificate server user

[2/8]: configuring certificate server instance

The next step is to get /root/ipa.csr signed by your CA and re-run /sbin/ipa-server-install as: /sbin/ipa-server-install --external-cert-file=/path/to/signed_certificate --external-cert-file=/path/to/external ca certificate

When this happens:

- a. Submit the CSR located in /**root/ipa.csr** to the external CA. The process differs depending on the service to be used as the external CA.
- b. Retrieve the issued certificate and the CA certificate chain for the issuing CA in a base 64-encoded blob (either a PEM file or a Base_64 certificate from a Windows CA). Again, the process differs for every certificate service. Usually, a download link on a web page or in the notification email allows the administrator to download all the required certificates.



IMPORTANT

Be sure to get the full certificate chain for the CA, not just the CA certificate.

c. Run **ipa-server-install** again, this time specifying the locations and names of the newly-issued CA certificate and the CA chain files. For example:

ipa-server-install --external-cert-file=/tmp/servercert20170601.pem --external-cert-file=/tmp/cacert.pem

- 9. The installation script now configures the server. Wait for the operation to complete.
- 10. After the installation script completes, update your DNS records in the following way:
 - a. Add DNS delegation from the parent domain to the IdM DNS domain. For example, if the IdM DNS domain is *idm.example.com*, add a name server (NS) record to the **example.com** parent domain.



IMPORTANT

Repeat this step each time after an IdM DNS server is installed.

b. Add an _ntp._udp service (SRV) record for your time server to your IdM DNS. The presence of the SRV record for the time server of the newly-installed IdM server in IdM DNS ensures that future replica and client installations are automatically configured to synchronize with the time server used by this primary IdM server.



NOTE

The **ipa-server-install --external-ca** command can sometimes fail with the following error:

ipa : CRITICAL failed to configure ca instance Command '/usr/sbin/pkispawn -s CA -f /tmp/configuration_file' returned non-zero exit status 1 Configuration of CA failed

This failure occurs when the *_proxy environmental variables are set. For a solution of the problem, see Section 3.2, "Troubleshooting: External CA installation fails".

3.2. TROUBLESHOOTING: EXTERNAL CA INSTALLATION FAILS

The **ipa-server-install --external-ca** command fails with the following error:

ipa : CRITICAL failed to configure ca instance Command '/usr/sbin/pkispawn -s CA -f /tmp/configuration_file' returned non-zero exit status 1 Configuration of CA failed

The **env|grep proxy** command displays variables such as the following:

env|grep proxy

http_proxy=http://example.com:8080 ftp_proxy=http://example.com:8080 https_proxy=http://example.com:8080

What this means:

The *_proxy environmental variables are preventing the server from being installed.

To fix the problem:

1. Use the following shell script to unset the *_proxy environmental variables:

for i in ftp https; do unset \${i}_proxy; done

2. Run the **pkidestroy** utility to remove the unsuccessful certificate authority (CA) subsystem installation:

pkidestroy -s CA -i pki-tomcat; rm -rf /var/log/pki/pki-tomcat /etc/sysconfig/pki-tomcat /etc/sysconfig/pki/tomcat/pki-tomcat /var/lib/pki/pki-tomcat /etc/pki/pki-tomcat /root/ipa.csr

3. Remove the failed Identity Management (IdM) server installation:

ipa-server-install --uninstall

4. Retry running ipa-server-install --external-ca.

CHAPTER 4. INSTALLING AN IDM SERVER: WITH INTEGRATED DNS, WITHOUT A CA

Installing a new Identity Management (IdM) server with integrated DNS has the following advantages:

- You can automate much of the maintenance and DNS record management using native IdM tools. For example, DNS SRV records are automatically created during the setup, and later on are automatically updated.
- You can have a stable connection with the rest of the Internet by setting up global forwarders
 during the installation of the IdM server. Global forwarders are also useful for trusts with Active
 Directory.
- You can set up a DNS reverse zone to prevent emails from your domain to be considered spam by email servers outside of the IdM domain.

Installing IdM with integrated DNS has certain limitations:

• IdM DNS is not meant to be used as a general-purpose DNS server. Some of the advanced DNS functions are not supported.

This chapter describes how you can install a new IdM server without a certificate authority (CA).

4.1. CERTIFICATES REQUIRED TO INSTALL AN IDM SERVER WITHOUT A CA

This section lists:

- the certificates required to install an Identity Management (IdM) server without a certificate authority (CA)
- the command-line options used to provide these certificates to the **ipa-server-install** utility



IMPORTANT

You cannot install a server or replica using self-signed third-party server certificates because the imported certificate files must contain the full CA certificate chain of the CA that issued the LDAP and Apache server certificates.

The LDAP server certificate and private key

- --dirsrv-cert-file for the certificate and private key files for the LDAP server certificate
- --dirsrv-pin for the password to access the private key in the files specified in --dirsrv-cert-file

The Apache server certificate and private key

- --http-cert-file for the certificate and private key files for the Apache server certificate
- --http-pin for the password to access the private key in the files specified in --http-cert-file

The full CA certificate chain of the CA that issued the LDAP and Apache server certificates

• --dirsrv-cert-file and --http-cert-file for the certificate files with the full CA certificate chain or a part of it

You can provide the files specified in the **--dirsrv-cert-file** and **--http-cert-file** options in the following formats:

- Privacy-Enhanced Mail (PEM) encoded certificate (RFC 7468). Note that the Identity Management installer accepts concatenated PEM-encoded objects.
- Distinguished Encoding Rules (DER)
- PKCS #7 certificate chain objects
- PKCS #8 private key objects
- PKCS #12 archives

You can specify the --dirsrv-cert-file and --http-cert-file options multiple times to specify multiple files.

The certificate files to complete the full CA certificate chain (not needed in some environments)

• **--ca-cert-file** for the file or files containing the CA certificate of the CA that issued the LDAP, Apache Server, and Kerberos KDC certificates. Use this option if the CA certificate is not present in the certificate files provided by the other options.

The files provided using **--dirsrv-cert-file** and **--http-cert-file** combined with the file provided using **--ca-cert-file** must contain the full CA certificate chain of the CA that issued the LDAP and Apache server certificates.

The Kerberos key distribution center (KDC) PKINIT certificate and private key (optional)

- --pkinit-cert-file for the Kerberos KDC SSL certificate and private key
- **--pkinit-pin** for the password to access the Kerberos KDC private key in the files specified in **--pkinit-cert-file**
- --no-pkinit for disabling pkinit setup steps

If you do not provide the PKINIT certificate, **ipa-server-install** configures the IdM server with a local KDC with a self-signed certificate.

Additional resources

- For details on what the certificate file formats these options accept, see the ipa-server-install(1) man page.
- For details on PKINIT extensions required to create a RHEL IdM PKINIT certificate, see this article.

4.2. INTERACTIVE INSTALLATION

During the interactive installation using the **ipa-server-install** utility, you are asked to supply basic configuration of the system, for example the realm, the administrator's password and the Directory Manager's password.

The **ipa-server-install** installation script creates a log file at /var/log/ipaserver-install.log. If the installation fails, the log can help you identify the problem.

Procedure

1. Run the **ipa-server-install** utility and provide all the required certificates. For example:

[root@server ~]# ipa-server-install \

- --http-cert-file /tmp/server.crt \
- --http-cert-file /tmp/server.key \
- --http-pin secret \
- --dirsrv-cert-file /tmp/server.crt \
- --dirsrv-cert-file /tmp/server.key \
- --dirsrv-pin secret \
- --ca-cert-file ca.crt

See Section 4.1, "Certificates required to install an IdM server without a CA" for details on the provided certificates.

2. The script prompts to configure an integrated DNS service. Enter **yes** or **no**. In this procedure, we are installing a server with integrated DNS.

Do you want to configure integrated DNS (BIND)? [no]: yes



NOTE

If you want to install a server without integrated DNS, the installation script will not prompt you for DNS configuration as described in the steps below. See Chapter 5, *Installing an IdM server: Without integrated DNS, with an integrated CA as the root CA* for details on the steps for installing a server without DNS.

- 3. The script prompts for several required settings and offers recommended default values in brackets.
 - To accept a default value, press **Enter**.
 - To provide a custom value, enter the required value.

Server host name [server.example.com]: Please confirm the domain name [example.com]: Please provide a realm name [EXAMPLE.COM]:



WARNING

Plan these names carefully. You will not be able to change them after the installation is complete.

4. Enter the passwords for the Directory Server superuser (**cn=Directory Manager**) and for the Identity Management (IdM) administration system user account (**admin**).

Directory Manager password: IPA admin password:

5. The script prompts for DNS forwarders.

Do you want to configure DNS forwarders? [yes]:

- To configure DNS forwarders, enter **yes**, and then follow the instructions on the command line. The installation process will add the forwarder IP addresses to the /etc/named.conf file on the installed IdM server.
 - For the forwarding policy default settings, see the **--forward-policy** description in the **ipa-dns-install**(1) man page.
- If you do not want to use DNS forwarding, enter no.
 With no DNS forwarders, your environment will be isolated, and names from other DNS domains in your infrastructure will not be resolved.
- 6. The script prompts to check if any DNS reverse (PTR) records for the IP addresses associated with the server need to be configured.

Do you want to search for missing reverse zones? [yes]:

If you run the search and missing reverse zones are discovered, the script asks you whether to create the reverse zones along with the PTR records.

Do you want to create reverse zone for IP 192.0.2.1 [yes]: Please specify the reverse zone name [2.0.192.in-addr.arpa.]: Using reverse zone(s) 2.0.192.in-addr.arpa.



NOTE

Using IdM to manage reverse zones is optional. You can use an external DNS service for this purpose instead.

- 7. Enter **yes** to confirm the server configuration.
 - Continue to configure the system with these values? [no]: yes
- 8. The installation script now configures the server. Wait for the operation to complete.
- 9. After the installation script completes, update your DNS records in the following way:
 - a. Add DNS delegation from the parent domain to the IdM DNS domain. For example, if the IdM DNS domain is *idm.example.com*, add a name server (NS) record to the *example.com* parent domain.



IMPORTANT

Repeat this step each time after an IdM DNS server is installed.

b. Add an _ntp._udp service (SRV) record for your time server to your IdM DNS. The presence of the SRV record for the time server of the newly-installed IdM server in IdM

DNS ensures that future replica and client installations are automatically configured to synchronize with the time server used by this primary IdM server.

CHAPTER 5. INSTALLING AN IDM SERVER: WITHOUT INTEGRATED DNS, WITH AN INTEGRATED CA AS THE ROOT CA

This chapter describes how you can install a new Identity Management (IdM) server without integrated DNS.



NOTE

Red Hat strongly recommends installing IdM-integrated DNS for basic usage within the IdM deployment: When the IdM server also manages DNS, there is tight integration between DNS and native IdM tools which enables automating some of the DNS record management.

For more details, see Planning your DNS services and host names .

5.1. INTERACTIVE INSTALLATION

During the interactive installation using the **ipa-server-install** utility, you are asked to supply basic configuration of the system, for example the realm, the administrator's password and the Directory Manager's password.

The **ipa-server-install** installation script creates a log file at **/var/log/ipaserver-install.log**. If the installation fails, the log can help you identify the problem.

This procedure installs a server:

- Without integrated DNS
- With integrated Identity Management (IdM) certificate authority (CA) as the root CA, which is the default CA configuration

Procedure

- 1. Run the **ipa-server-install** utility.
 - # ipa-server-install
- 2. The script prompts to configure an integrated DNS service. Press **Enter** to select the default **no** option.
 - Do you want to configure integrated DNS (BIND)? [no]:
- 3. The script prompts for several required settings and offers recommended default values in brackets.
 - To accept a default value, press **Enter**.
 - To provide a custom value, enter the required value.

Server host name [server.example.com]: Please confirm the domain name [example.com]: Please provide a realm name [EXAMPLE.COM]:



WARNING

Plan these names carefully. You will not be able to change them after the installation is complete.

4. Enter the passwords for the Directory Server superuser (**cn=Directory Manager**) and for the IdM administration system user account (**admin**).

Directory Manager password: IPA admin password:

- 5. Enter **yes** to confirm the server configuration.
 - Continue to configure the system with these values? [no]: yes
- 6. The installation script now configures the server. Wait for the operation to complete.
- 7. The installation script produces a file with DNS resource records: **the**/**tmp/ipa.system.records.UFRPto.db** file in the example output below. Add these records to the existing external DNS servers. The process of updating the DNS records varies depending on the particular DNS solution.

Restarting the KDC

Please add records in this file to your DNS system:
/tmp/ipa.system.records.UFRBto.db

Restarting the web server



IMPORTANT

The server installation is not complete until you add the DNS records to the existing DNS servers.

Additional resources

 For more information about the DNS resource records you must add to your DNS system, see IdM DNS records for external DNS systems.

5.2. NON-INTERACTIVE INSTALLATION

This procedure installs a server:

- Without integrated DNS
- With integrated Identity Management (IdM) certificate authority (CA) as the root CA, which is the default CA configuration



NOTE

The **ipa-server-install** installation script creates a log file at /**var/log/ipaserver-install.log**. If the installation fails, the log can help you identify the problem.

Procedure

- 1. Run the **ipa-server-install** utility with the options to supply all the required information. The minimum required options for non-interactive installation are:
 - --realm to provide the Kerberos realm name
 - --ds-password to provide the password for the Directory Manager (DM), the Directory Server super user
 - --admin-password to provide the password for admin, the IdM administrator
 - **--unattended** to let the installation process select default options for the host name and domain name

For example:

ipa-server-install --realm *EXAMPLE.COM* --ds-password *DM_password* --admin-password admin_password --unattended

2. The installation script produces a file with DNS resource records: **the**/**tmp/ipa.system.records.UFRPto.db** file in the example output below. Add these records to the existing external DNS servers. The process of updating the DNS records varies depending on the particular DNS solution.

...

Restarting the KDC

Please add records in this file to your DNS system: /tmp/ipa.system.records.UFRBto.db
Restarting the web server

...



IMPORTANT

The server installation is not complete until you add the DNS records to the existing DNS servers.

Additional resources

- For more information about the DNS resource records you must add to your DNS system, see IdM DNS records for external DNS systems .
- For a complete list of options accepted by **ipa-server-install**, run the **ipa-server-install --help** command.

5.3. IDM DNS RECORDS FOR EXTERNAL DNS SYSTEMS

After installing an IdM server without integrated DNS, you must add LDAP and Kerberos DNS resource records for the IdM server to your external DNS system.

The **ipa-server-install** installation script generates a file containing the list of DNS resource records with a file name in the format /tmp/ipa.system.records.</ri>

Please add records in this file to your DNS system: /tmp/ipa.system.records.6zdjqxh3.db

This is an example of the contents of the file:

- kerberos-master. tcp.example.com. 86400 IN SRV 0 100 88 server.example.com.
- _kerberos-master._udp.example.com. 86400 IN SRV 0 100 88 server.example.com.
- _kerberos._tcp.example.com. 86400 IN SRV 0 100 88 server.example.com.
- _kerberos._udp.example.com. 86400 IN SRV 0 100 88 server.example.com.
- _kerberos.example.com. 86400 IN TXT "EXAMPLE.COM"
- _kpasswd._tcp.example.com. 86400 IN SRV 0 100 464 server.example.com.
- _kpasswd._udp.example.com. 86400 IN SRV 0 100 464 server.example.com.
- _ldap._tcp.example.com. 86400 IN SRV 0 100 389 server.example.com.



NOTE

After adding the LDAP and Kerberos DNS resource records for the IdM server to your DNS system, ensure that the DNS management tools have not added PTR records for **ipa-ca**. The presence of PTR records for **ipa-ca** in your DNS could cause subsequent IdM replica installations to fail.

CHAPTER 6. INSTALLING AN IDM SERVER: WITHOUT INTEGRATED DNS, WITH AN EXTERNAL CA AS THE ROOT CA

This chapter describes how you can install a new Identity Management (IdM) server, without integrated DNS, that uses an external certificate authority (CA) as the root CA.



NOTE

Red Hat strongly recommends installing IdM-integrated DNS for basic usage within the IdM deployment: When the IdM server also manages DNS, there is tight integration between DNS and native IdM tools which enables automating some of the DNS record management.

For more details, see Planning your DNS services and host names.

6.1. INTERACTIVE INSTALLATION

During the interactive installation using the **ipa-server-install** utility, you are asked to supply basic configuration of the system, for example the realm, the administrator's password and the Directory Manager's password.

The **ipa-server-install** installation script creates a log file at /**var/log/ipaserver-install.log**. If the installation fails, the log can help you identify the problem.

This procedure describes how to install a server:

- Without integrated DNS
- With an external certificate authority (CA) as the root CA

Prerequisites

- Decide on the type of the external CA you use (the **--external-ca-type** option). See the **ipa-server-install**(1) man page for details.
- Alternatively, decide on the --external-ca-profile option allowing an alternative Active Directory Certificate Services (AD CS) template to be specified. For example, to specify an AD CS installation-specific object identifier:

[root@server ~]# ipa-server-install --external-ca --external-ca-type=ms-cs --external-ca-profile=1.3.6.1.4.1.311.21.8.8950086.10656446.2706058.12775672.480128.147.7130143.44 05632:1

Procedure

1. Run the **ipa-server-install** utility with the **--external-ca** option.

ipa-server-install --external-ca

If you are using the Microsoft Certificate Services CA, use also the **--external-ca-type** option. For details, see the **ipa-server-install** (1) man page.

2. The script prompts to configure an integrated DNS service. Press **Enter** to select the default **no** option.

Do you want to configure integrated DNS (BIND)? [no]:

- 3. The script prompts for several required settings and offers recommended default values in brackets.
 - To accept a default value, press Enter.
 - To provide a custom value, enter the required value.

Server host name [*server.example.com*]: Please confirm the domain name [*example.com*]: Please provide a realm name [*EXAMPLE.COM*]:



WARNING

Plan these names carefully. You will not be able to change them after the installation is complete.

4. Enter the passwords for the Directory Server superuser (**cn=Directory Manager**) and for the IdM administration system user account (**admin**).

Directory Manager password: IPA admin password:

5. Enter **yes** to confirm the server configuration.

Continue to configure the system with these values? [no]: **yes**

6. During the configuration of the Certificate System instance, the utility prints the location of the certificate signing request (CSR): /root/ipa.csr:

...

Configuring certificate server (pki-tomcatd): Estimated time 3 minutes 30 seconds

[1/8]: creating certificate server user

[2/8]: configuring certificate server instance

The next step is to get /root/ipa.csr signed by your CA and re-run /sbin/ipa-server-install as: /sbin/ipa-server-install --external-cert-file=/path/to/signed_certificate --external-cert-file=/path/to/external_ca_certificate

When this happens:

- a. Submit the CSR located in /**root/ipa.csr** to the external CA. The process differs depending on the service to be used as the external CA.
- b. Retrieve the issued certificate and the CA certificate chain for the issuing CA in a base 64-encoded blob (either a PEM file or a Base_64 certificate from a Windows CA). Again, the process differs for every certificate service. Usually, a download link on a web page or in the notification email allows the administrator to download all the required certificates.



IMPORTANT

Be sure to get the full certificate chain for the CA, not just the CA certificate.

c. Run **ipa-server-install** again, this time specifying the locations and names of the newly-issued CA certificate and the CA chain files. For example:

ipa-server-install --external-cert-file=/tmp/servercert20170601.pem --external-cert-file=/tmp/cacert.pem

- 7. The installation script now configures the server. Wait for the operation to complete.
- 8. The installation script produces a file with DNS resource records: **the**/**tmp/ipa.system.records.UFRPto.db** file in the example output below. Add these records to the existing external DNS servers. The process of updating the DNS records varies depending on the particular DNS solution.

Restarting the KDC

Please add records in this file to your DNS system:
/tmp/ipa.system.records.UFRBto.db

Restarting the web server



IMPORTANT

The server installation is not complete until you add the DNS records to the existing DNS servers.

Additional resources

- For more information about the DNS resource records you must add to your DNS system, see IdM DNS records for external DNS systems.
- The **ipa-server-install --external-ca** command can sometimes fail with the following error:

ipa : CRITICAL failed to configure ca instance Command '/usr/sbin/pkispawn -s CA -f /tmp/pass:quotes[configuration_file]' returned non-zero exit status 1 Configuration of CA failed

This failure occurs when the *_proxy environmental variables are set. For a solution of the problem, see Section 3.2, "Troubleshooting: External CA installation fails".

6.2. NON-INTERACTIVE INSTALLATION

This procedure installs a server:

- Without integrated DNS
- with an external certificate authority (CA) as the root CA



NOTE

The **ipa-server-install** installation script creates a log file at /**var/log/ipaserver-install.log**. If the installation fails, the log can help you identify the problem.

Prerequisites

- Decide on the type of the external CA you use (the --external-ca-type option). See the ipa-server-install(1) man page for details.
- Alternatively, decide on the --external-ca-profile option allowing an alternative Active Directory Certificate Services (AD CS) template to be specified. For example, to specify an AD CS installation-specific object identifier:

[root@server ~]# ipa-server-install --external-ca --external-ca-type=ms-cs --external-ca-profile=1.3.6.1.4.1.311.21.8.8950086.10656446.2706058.12775672.480128.147.7130143.44 05632:1

Procedure

- 1. Run the **ipa-server-install** utility with the options to supply all the required information. The minimum required options for non-interactive installation of an IdM server with an external CA as the root CA are:
 - --external-ca to specify an external CA is the root CA
 - --realm to provide the Kerberos realm name
 - **--ds-password** to provide the password for the Directory Manager (DM), the Directory Server super user
 - --admin-password to provide the password for admin, the IdM administrator
 - --unattended to let the installation process select default options for the host name and domain name

For example:

ipa-server-install --external-ca --realm *EXAMPLE.COM* --ds-password *DM_password* --admin-password admin_password --unattended

If you are using the Microsoft Certificate Services CA, use also the **--external-ca-type** option. For details, see the **ipa-server-install** (1) man page.

2. During the configuration of the Certificate System instance, the utility prints the location of the certificate signing request (CSR): /root/ipa.csr:

...

Configuring certificate server (pki-tomcatd). Estimated time: 3 minutes

[1/11]: configuring certificate server instance

The next step is to get /root/ipa.csr signed by your CA and re-run /usr/sbin/ipa-server-install as:

/usr/sbin/ipa-server-install --external-cert-file=/path/to/signed_certificate --external-cert-file=/path/to/external_ca_certificate

The ipa-server-install command was successful

When this happens:

- a. Submit the CSR located in /**root/ipa.csr** to the external CA. The process differs depending on the service to be used as the external CA.
- b. Retrieve the issued certificate and the CA certificate chain for the issuing CA in a base 64-encoded blob (either a PEM file or a Base_64 certificate from a Windows CA). Again, the process differs for every certificate service. Usually, a download link on a web page or in the notification email allows the administrator to download all the required certificates.



IMPORTANT

Be sure to get the full certificate chain for the CA, not just the CA certificate.

c. Run **ipa-server-install** again, this time specifying the locations and names of the newly-issued CA certificate and the CA chain files. For example:

ipa-server-install --external-cert-file=/tmp/servercert20170601.pem --external-cert-file=/tmp/cacert.pem --realm EXAMPLE.COM --ds-password DM_password --admin-password admin_password --unattended

- 3. The installation script now configures the server. Wait for the operation to complete.
- 4. The installation script produces a file with DNS resource records: the /tmp/ipa.system.records.UFRPto.db file in the example output below. Add these records to the existing external DNS servers. The process of updating the DNS records varies depending on the particular DNS solution.

Restarting the KDC
Please add records in this file to your DNS system:
/tmp/ipa.system.records.UFRBto.db
Restarting the web server



IMPORTANT

The server installation is not complete until you add the DNS records to the existing DNS servers.

Additional resources

 For more information about the DNS resource records you must add to your DNS system, see IdM DNS records for external DNS systems.

6.3. IDM DNS RECORDS FOR EXTERNAL DNS SYSTEMS

After installing an IdM server without integrated DNS, you must add LDAP and Kerberos DNS resource records for the IdM server to your external DNS system.

The **ipa-server-install** installation script generates a file containing the list of DNS resource records with a file name in the format /tmp/ipa.system.records.</ri>

Please add records in this file to your DNS system: /tmp/ipa.system.records.6zdjqxh3.db

This is an example of the contents of the file:

- _kerberos-master._tcp.example.com. 86400 IN SRV 0 100 88 server.example.com.
- _kerberos-master._udp.example.com. 86400 IN SRV 0 100 88 server.example.com.
- _kerberos._tcp.example.com. 86400 IN SRV 0 100 88 server.example.com.
- _kerberos._udp.example.com. 86400 IN SRV 0 100 88 server.example.com.
- _kerberos.example.com. 86400 IN TXT "EXAMPLE.COM"
- _kpasswd._tcp.example.com. 86400 IN SRV 0 100 464 server.example.com.
- _kpasswd._udp.example.com. 86400 IN SRV 0 100 464 server.example.com.
- _ldap._tcp.example.com. 86400 IN SRV 0 100 389 server.example.com.



NOTE

After adding the LDAP and Kerberos DNS resource records for the IdM server to your DNS system, ensure that the DNS management tools have not added PTR records for **ipa-ca**. The presence of PTR records for **ipa-ca** in your DNS could cause subsequent IdM replica installations to fail.

CHAPTER 7. TROUBLESHOOTING IDM SERVER INSTALLATION

The following sections describe how to gather information about a failing IdM server installation, and how to resolve common installation issues.

- Reviewing IdM server installation error logs
- Reviewing IdM CA installation errors
- Removing a partial IdM server installation

7.1. REVIEWING IDM SERVER INSTALLATION ERROR LOGS

When you install an Identity Management (IdM) server, debugging information is appended to the following log files:

- /var/log/ipaserver-install.log
- /var/log/httpd/error_log
- /var/log/dirsrv/slapd-INSTANCE-NAME/access
- /var/log/dirsrv/slapd-INSTANCE-NAME/errors

The last lines of the log files report success or failure, and the **ERROR** and **DEBUG** entries provide additional context.

To troubleshoot a failing IdM server installation, review the errors at the end of the log files and use this information to resolve any corresponding issues.

Prerequisites

• You must have **root** privileges to display the contents of IdM log files.

Procedure

1. Use the **tail** command to display the last lines of a log file. The following example displays the last 10 lines of /var/log/ipaserver-install.log.

[user@server ~]\$ sudo tail -n 10 /var/log/ipaserver-install.log

[sudo] password for user:

value = gen.send(prev value)

File "/usr/lib/python3.6/site-packages/ipapython/install/common.py", line 65, in _install for unused in self. installer(self.parent):

File "/usr/lib/python3.6/site-packages/ipaserver/install/server/*init*.py", line 564, in main master install(self)

File "/usr/lib/python3.6/site-packages/ipaserver/install/server/install.py", line 291, in decorated raise ScriptError()

2020-05-27T22:59:41Z DEBUG The ipa-server-install command failed, exception: ScriptError:

2020-05-27T22:59:41Z ERROR The ipa-server-install command failed. See /var/log/ipaserver-install.log for more information

2. To review a log file interactively, open the end of the log file using the **less** utility and use the ↑ and ↓ arrow keys to navigate. The following example opens the /var/log/ipaserver-install.log file interactively.

[user@server ~]\$ sudo less -N +G /var/log/ipaserver-install.log

3. Gather additional troubleshooting information by repeating this review process with the remaining log files.

[user@server ~]\$ sudo less -N +G /var/log/httpd/error_log

[user@server ~]\$ sudo less -N +G /var/log/dirsrv/slapd-INSTANCE-NAME/access

[user@server ~]\$ sudo less -N +G /var/log/dirsrv/slapd-INSTANCE-NAME/errors

Additional resources

- If you are unable to resolve a failing IdM server installation, and you have a Red Hat Technical Support subscription, open a Technical Support case at the Red Hat Customer Portal and provide an **sosreport** of the server.
- The **sosreport** utility collects configuration details, logs and system information from a RHEL system. For more information on the **sosreport** utility, see What is an sosreport and how to create one in Red Hat Enterprise Linux?.

7.2. REVIEWING IDM CA INSTALLATION ERRORS

When you install the Certificate Authority (CA) service on an Identity Management (IdM) server, debugging information is appended to the following locations (in order of recommended priority):

Location	Description
/var/log/pki/pki-ca- spawn. <i>\$TIME_OF_INSTALLATION</i> .log	High-level issues and Python traces for the pkispawn installation process
journalctl -u pki-tomcatd@pki-tomcat output	Errors from the pki-tomcatd@pki-tomcat service
/var/log/pki/pki-tomcat/ca/debug.\$DATE.log	Large JAVA stacktraces of activity in the core of the Public Key Infrastructure (PKI) product
/var/log/pki/pki- tomcat/ca/signedAudit/ca_audit log file	Audit log of the PKI product
 /var/log/pki/pki-tomcat/ca/system /var/log/pki/pki-tomcat/ca/transactions /var/log/pki/pki-tomcat/catalina.\$DATE.log 	Low-level debug data of certificate operations for service principals, hosts, and other entities that use certificates



NOTE

If a full IdM server installation fails while installing the optional CA component, no details about the CA are logged; a message is logged in the /var/log/ipaserver-install.log file indicating that the overall installation process failed. Red Hat recommends reviewing the log files listed above for details specific to the CA installation failure.

The only exception to this behavior is when you are installing the CA service and the root CA is an external CA. If there is an issue with the certificate from the external CA, errors are logged in /var/log/ipaserver-install.log.

To troubleshoot a failing IdM CA installation, review the errors at the end of these log files and use this information to resolve any corresponding issues.

Prerequisites

• You must have **root** privileges to display the contents of IdM log files.

Procedure

- To review a log file interactively, open the end of the log file using the less utility and use the ↑ and ↓ arrow keys to navigate, while searching for ScriptError entries. The following example opens /var/log/pki/pki-ca-spawn.\$TIME_OF_INSTALLATION.log.
 - [user@server ~]\$ sudo less -N +G /var/log/pki/pki-ca-spawn.20200527185902.log
- 2. Gather additional troubleshooting information by repeating this review process with all the log files listed above.

Additional resources

- If you are unable to resolve a failing IdM server installation, and you have a Red Hat Technical Support subscription, open a Technical Support case at the Red Hat Customer Portal and provide an **sosreport** of the server.
- The sosreport utility collects configuration details, logs and system information from a RHEL system. For more information on the sosreport utility, see What is an sosreport and how to create one in Red Hat Enterprise Linux?.

7.3. REMOVING A PARTIAL IDM SERVER INSTALLATION

If an IdM server installation fails, some configuration files can be left behind. Additional attempts to install the IdM server fail and the installation script reports that IPA is already configured.

[root@server ~]# ipa-server-install

The log file for this installation can be found in /var/log/ipaserver-install.log

IPA server is already configured on this system.

If you want to reinstall the IPA server, **please uninstall it first using 'ipa-server-install --uninstall'**. The ipa-server-install command failed. See /var/log/ipaserver-install.log for more information

To resolve this issue, uninstall the partial IdM server configuration and retry the installation process.

Prerequisites

• You must have **root** privileges.

Procedure

- 1. Uninstall the IdM server software from the host you are trying to configure as an IdM server.
 - [root@server ~]# ipa-server-install --uninstall
- 2. If you continue to experience difficulty installing an IdM server because of repeated failed installations, reinstall the operating system.
 - One of the requirements for installing an IdM server is a clean system without any customization. Failed installations may have compromised the integrity of the host by unexpectedly modifying system files.

Additional resources

- For additional details on uninstalling an IdM server, see Uninstalling an IdM server.
- If installation attempts fail after repeated uninstallation attempts, and you have a Red Hat Technical Support subscription, open a Technical Support case at the Red Hat Customer Portal and provide an **sosreport** of the server.
- The sosreport utility collects configuration details, logs and system information from a RHEL system. For more information on the sosreport utility, see What is an sosreport and how to create one in Red Hat Enterprise Linux?.

7.4. ADDITIONAL RESOURCES

- To troubleshoot installing an IdM replica, see Troubleshooting IdM replica installation.
- To troubleshoot installing an IdM client, see Troubleshooting IdM client installation .

CHAPTER 8. UNINSTALLING AN IDM SERVER

As an administrator, you can remove an Identity Management (IdM) server from the topology.

This procedure describes how you can uninstall an example server named **server.idm.example.com**.

Prerequisites

• Before uninstalling a server that serves as a certificate authority (CA), key recovery authority (KRA), or DNS server, make sure these services are running on another server in the domain.



WARNING

Removing the last server that serves as a CA, KRA, or DNS server seriously disrupts the Identity Management (IdM) functionality.

Procedure

- 1. On another server, enter the **ipa server-del** command to delete **server.idm.example.com** from the topology:
 - [root@another_server ~]# ipa server-del server.idm.example.com
- 2. On server.idm.example.com, use the ipa-server-install --uninstall command:

[root@server ~]# ipa-server-install --uninstall ...

Are you sure you want to continue with the uninstall procedure? [no]: yes

3. Make sure all name server (NS) DNS records pointing to **server.idm.example.com** are deleted from your DNS zones. This applies regardless of whether you use integrated DNS managed by IdM or external DNS.

CHAPTER 9. RENAMING AN IDM SERVER

You cannot change the host name of an existing Identity Management (IdM) server. However, you can replace the server with a replica of a different name.

Procedure

1. Install a new replica that will replace the existing server, ensuring the replica has the required host name and IP address. For details, see Chapter 18, Installing an IdM replica.



IMPORTANT

If the server you are uninstalling is the certificate revocation list (CRL) publisher server, make another server the CRL publisher server before proceeding. For details how this is done in the context of a migration procedure, see the following sections:

- Stopping CRL generation on a RHEL 7 IdM CA server
- Starting CRL generation on the new RHEL 8 IdM CA server
- 2. Stop the existing IdM server instance.

[root@old_server ~]# ipactl stop

3. Uninstall the existing server as described in Chapter 8, *Uninstalling an IdM server*.

CHAPTER 10. PREPARING THE SYSTEM FOR IDM CLIENT INSTALLATION

This chapter describes the conditions your system must meet to install an Identity Management (IdM) client.

10.1. DNS REQUIREMENTS FOR IDM CLIENTS

Client installer by default tries to search for _ldap._tcp.DOMAIN DNS SRV records for all domains that are parent to its hostname. For example, if a client machine has a hostname client1.idm.example.com, the installer will try to retrieve an IdM server hostname from _ldap._tcp.idm.example.com, _ldap._tcp.example.com and _ldap._tcp.com DNS SRV records, respectively. The discovered domain is then used to configure client components (for example, SSSD and Kerberos 5 configuration) on the machine.

However, the hostnames of IdM clients are not required to be part of the primary DNS domain. If the client machine hostname is not in a subdomain of an IdM server, pass the IdM domain as the **--domain** option of the **ipa-client-install** command. In that case, after the installation of the client, both SSSD and Kerberos components will have the domain set in their configuration files and will use it to autodiscover IdM servers.

Additional resources

 For details on DNS requirements in IdM, see Section 1.5, "Host name and DNS requirements for IdM".

10.2. PORT REQUIREMENTS FOR IDM CLIENTS

Identity Management (IdM) clients connect to a number of ports on IdM servers to communicate with their services.

On IdM client, these ports must be open in the outgoing direction. If you are using a firewall that does not filter outgoing packets, such as **firewalld**, the ports are already available in the outgoing direction.

Additional resources

 For information about which specific ports are used, see Section 1.6, "Port requirements for IdM"

10.3. IPV6 REQUIREMENTS FOR IDM CLIENTS

Identity Management (IdM) does not require the **IPv6** protocol to be enabled in the kernel of the host that you want to enroll into IdM. For example, if your internal network only uses the **IPv4** protocol, you can configure the System Security Services Daemon (SSSD) to only use **IPv4** to communicate with the IdM server. You can do this by inserting the following line into the **[domain/NAME]** section of the **/etc/sssd/sssd.conf** file:

lookup_family_order = ipv4_only

Additional resources

• For more information on the **lookup_family_order** option, see the **sssd.conf(5)** man page.

10.4. PACKAGES REQUIRED TO INSTALL AN IDM CLIENT

In RHEL8, the packages necessary for installing an Identity Management (IdM) client are shipped as a module. Two IdM streams provide IdM client packages:

- the **idm:client** stream. For details, see Section 10.4.1, "Installing ipa-client packages from the idm:client stream".
- the **idm:DL1** stream. For details, see Section 10.4.2, "Installing ipa-client packages from the idm:DL1 stream".

10.4.1. Installing ipa-client packages from the idm:client stream

The **idm:client** stream is the default stream of the **idm** module. Use this stream to download the IdM client packages if you do not need to install server components on your machine. Using the **idm:client** stream is especially recommended if you need to consistently use IdM client software that is supported long-term, provided you do not need server components, too.



IMPORTANT

When switching to the **idm:client** stream after you previously enabled the **idm:DL1** stream and downloaded packages from it, you need to first explicitly remove all the relevant installed content and disable the **idm:DL1** stream before enabling the **idm:client** stream. Trying to enable a new stream without disabling the current one results in an error. For details on how to proceed, see Switching to a later stream.

Procedure

To download the packages necessary for installing an IdM client:

yum module install idm

10.4.2. Installing ipa-client packages from the idm:DL1 stream

The **idm:DL1** stream needs to be enabled before you can download packages from it. Use this stream to download the IdM client packages if you need to install IdM server components on your machine.



IMPORTANT

When switching to the <code>idm:DL1</code> stream after you previously enabled the <code>idm:client</code> stream and downloaded packages from it, you need to first explicitly remove all the relevant installed content and disable the <code>idm:client</code> stream before enabling the <code>idm:DL1</code> stream. Trying to enable a new stream without disabling the current one results in an error. For details on how to proceed, see <code>Switching</code> to a later stream .

Procedure

1. To switch to the RPMs delivered through the **idm:DL1** stream:

yum module enable idm:DL1
yum distro-sync

2. To download the packages necessary for installing an IdM client:

-

yum module install idm:DL1/client

CHAPTER 11. INSTALLING AN IDM CLIENT: BASIC SCENARIO

The following sections describe how to configure a system as an Identity Management (IdM) client by using the **ipa-client-install** utility. Configuring a system as an IdM client enrolls it into an IdM domain and enables the system to use IdM services on IdM servers in the domain.

To install an Identity Management (IdM) client successfully, you must provide credentials that can be used to enroll the client. The following authentication methods are available:

- For installing a client interactively using privileged user's credentials (the default option), see Installing a client by using user credentials: Interactive installation.
- For installing a client interactively using a one-time password, see Installing a client by using a one-time password: Interactive installation.
- For installing a client noninteractively using either a privileged user's credentials, a one-time password or a keytab from a previous enrollment, see Installing a client: Non-interactive installation.

11.1. PREREQUISITES

Before you start installing the IdM client, make sure that you have met all the prerequisites. See Chapter 10, *Preparing the system for IdM client installation*.

11.2. INSTALLING A CLIENT BY USING USER CREDENTIALS: INTERACTIVE INSTALLATION

This procedure describes installing an Identity Management (IdM) client interactively by using the credentials of an authorized user to enroll the system into the domain.

Prerequisites

• Ensure you have the credentials of a user authorized to enroll clients into the IdM domain. This could be, for example, a **hostadmin** user with the Enrollment Administrator role.

Procedure

1. Run the ipa-client-install utility on the system that you want to configure as an IdM client.

ipa-client-install --mkhomedir

Add the **--enable-dns-updates** option to update the DNS records with the IP address of the client system if either of the following conditions applies:

- The IdM server the client will be enrolled with was installed with integrated DNS
- The DNS server on the network accepts DNS entry updates with the GSS-TSIG protocol

ipa-client-install --enable-dns-updates --mkhomedir

Enabling DNS updates is useful if your client:

• has a dynamic IP address issued using the Dynamic Host Configuration Protocol

- has a static IP address but it has just been allocated and the IdM server does not know about it
- 2. The installation script attempts to obtain all the required settings, such as DNS records, automatically.
 - If the SRV records are set properly in the IdM DNS zone, the script automatically discovers all the other required values and displays them. Enter **yes** to confirm.

Client hostname: client.example.com

Realm: EXAMPLE.COM
DNS Domain: example.com
IPA Server: server.example.com
BaseDN: dc=example,dc=com

Continue to configure the system with these values? [no]: yes

- To install the system with different values, enter no. Then run ipa-client-install again, and specify the required values by adding command-line options to ipa-client-install, for example:
 - --hostname
 - --realm
 - --domain
 - o --server
 - o --mkhomedir
- If the script fails to obtain some settings automatically, it prompts you for the values.



IMPORTANT

The fully qualified domain name must be a valid DNS name:

- Only numbers, alphabetic characters, and hyphens (-) are allowed. For example, underscores are not allowed and can cause DNS failures.
- The host name must be all lower-case. No capital letters are allowed.
- 3. The script prompts for a user whose identity will be used to enroll the client. This could be, for example, a **hostadmin** user with the Enrollment Administrator role:

User authorized to enroll computers: **hostadmin** Password for **hostadmin@EXAMPLE.COM**:

4. The installation script now configures the client. Wait for the operation to complete.

Client configuration complete.

Additional resources

• For details on how the client installation script searches for the DNS records, see the **DNS Autodiscovery** section in the **ipa-client-install**(1) man page.

11.3. INSTALLING A CLIENT BY USING A ONE-TIME PASSWORD: INTERACTIVE INSTALLATION

This procedure describes installing an Identity Management (IdM) client interactively by using a one-time password to enroll the system into the domain.

Prerequisites

1. On a server in the domain, add the future client system as an IdM host. Use the **--random** option with the **ipa host-add** command to generate a one-time random password for the enrollment.

\$ ipa host-add client.example.com --random

Added host "client.example.com"

Host name: client.example.com Random password: **W5YpARI=7M.n**

Password: True Keytab: False

Managed by: server.example.com



NOTE

The generated password will become invalid after you use it to enroll the machine into the IdM domain. It will be replaced with a proper host keytab after the enrollment is finished.

Procedure

1. Run the **ipa-client-install** utility on the system that you want to configure as an IdM client. Use the **--password** option to provide the one-time random password. Because the password often contains special characters, enclose it in single quotes (').

ipa-client-install --mkhomedir

Add the **--enable-dns-updates** option to update the DNS records with the IP address of the client system if either of the following conditions applies:

- The IdM server the client will be enrolled with was installed with integrated DNS
- The DNS server on the network accepts DNS entry updates with the GSS-TSIG protocol

ipa-client-install --password 'W5YpARI=7M.n' --enable-dns-updates --mkhomedir

Enabling DNS updates is useful if your client:

- has a dynamic IP address issued using the Dynamic Host Configuration Protocol
- has a static IP address but it has just been allocated and the IdM server does not know about it

- 2. The installation script attempts to obtain all the required settings, such as DNS records, automatically.
 - If the SRV records are set properly in the IdM DNS zone, the script automatically discovers all the other required values and displays them. Enter **yes** to confirm.

Client hostname: client.example.com

Realm: EXAMPLE.COM
DNS Domain: example.com
IPA Server: server.example.com
BaseDN: dc=example,dc=com

Continue to configure the system with these values? [no]: yes

- To install the system with different values, enter no. Then run ipa-client-install again, and specify the required values by adding command-line options to ipa-client-install, for example:
 - o --hostname
 - o --realm
 - --domain
 - --server
 - --mkhomedir
- If the script fails to obtain some settings automatically, it prompts you for the values.



IMPORTANT

The fully qualified domain name must be a valid DNS name:

- Only numbers, alphabetic characters, and hyphens (-) are allowed. For example, underscores are not allowed and can cause DNS failures.
- The host name must be all lower-case. No capital letters are allowed.
- 3. The installation script now configures the client. Wait for the operation to complete.
 - Client configuration complete.

Additional resources

For details on how the client installation script searches for the DNS records, see the DNS
 Autodiscovery section in the ipa-client-install(1) man page.

11.4. INSTALLING A CLIENT: NON-INTERACTIVE INSTALLATION

For a non-interactive installation, you must provide all required information to the **ipa-client-install** utility using command-line options. The following sections describe the minimum required options for a non-interactive installation.

Options for the intended authentication method for client enrollment

The available options are:

- --principal and --password to specify the credentials of a user authorized to enroll clients
- -random to specify a one-time random password generated for the client
- --keytab to specify the keytab from a previous enrollment

The option for unattended installation

The **--unattended** option lets the installation run without requiring user confirmation. If the SRV records are set properly in the IdM DNS zone, the script automatically discovers all the other required values. If the script cannot discover the values automatically, provide them using command-line options, such as:

• --hostname to specify a static fully qualified domain name (FQDN) for the client machine.



IMPORTANT

The FQDN must be a valid DNS name:

- Only numbers, alphabetic characters, and hyphens (-) are allowed. For example, underscores are not allowed and can cause DNS failures.
- The host name must be all lower-case. No capital letters are allowed.
- **--domain** to specify the primary DNS domain of an existing IdM deployment, e.g. example.com. The name is a lowercase version of the IdM Kerberos realm name.
- **--server** to specify the FQDN of the IdM server to connect to. When this option is used, DNS autodiscovery for Kerberos is disabled and a fixed list of KDC and Admin servers is configured. Under normal circumstances, this option is not needed as the list of servers is retrieved from the primary IdM DNS domain.
- --realm to specify the Kerberos realm of an existing IdM deployment. Usually it is an
 uppercase version of the primary DNS domain used by the IdM installation. Under normal
 circumstances, this option is not needed as the realm name is retrieved from the IdM server.

An example of a basic ipa-client-install command for non-interactive installation:

ipa-client-install --password 'W5YpARI=7M.n' --mkhomedir --unattended

An example of an **ipa-client-install** command for non-interactive installation with more options specified:

ipa-client-install --password 'W5YpARI=7M.n' --domain idm.example.com --server server.idm.example.com --realm IDM.EXAMPLE.COM --mkhomedir --unattended

Additional resources

 For a complete list of options accepted by ipa-client-install, see the ipa-client-install (1) man page.

11.5. REMOVING PRE-IDM CONFIGURATION AFTER INSTALLING A CLIENT

The **ipa-client-install** script does not remove any previous LDAP and System Security Services Daemon (SSSD) configuration from the **/etc/openIdap/Idap.conf** and **/etc/sssd/sssd.conf** files. If you modified the configuration in these files before installing the client, the script adds the new client values, but comments them out. For example:

BASE dc=example,dc=com URI ldap://ldap.example.com

#URI Idaps://server.example.com # modified by IPA #BASE dc=ipa,dc=example,dc=com # modified by IPA

To apply the new Identity Management (IdM)} configuration values:

- Open /etc/openIdap/Idap.conf and /etc/sssd/sssd.conf.
- 2. Delete the previous configuration.
- 3. Uncomment the new IdM configuration.
- 4. Server processes that rely on system-wide LDAP configuration might require a restart to apply the changes. Applications that use **openIdap** libraries typically import the configuration when started.

11.6. TESTING AN IDM CLIENT

The command-line interface informs you that the **ipa-client-install** was successful, but you can also do your own test.

To test that the Identity Management (IdM) client can obtain information about users defined on the server, check that you are able to resolve a user defined on the server. For example, to check the default **admin** user:

[user@client ~]\$ **id admin** uid=1254400000(admin) gid=1254400000(admins) groups=1254400000(admins)

To test that authentication works correctly, ${\bf su}$ to a root user from a non-root user:

[user@client ~]\$ **su -**Last login: Thu Oct 18 18:39:11 CEST 2018 from 192.168.122.1 on pts/0
[root@client ~]#

11.7. CONNECTIONS PERFORMED DURING AN IDM CLIENT INSTALLATION

Table 11.1, "Requests performed during an IdM client installation" lists the operations performed by **ipa-client-install**, the Identity Management (IdM) client installation tool.

Table 11.1. Requests performed during an IdM client installation

Operation	Protocol used	Purpose
DNS resolution against the DNS resolvers configured on the client system	DNS	To discover the IP addresses of IdM servers; (optionally) to add A/AAAA and SSHFP records
Requests to ports 88 (TCP/TCP6 and UDP/UDP6) on an IdM replica	Kerberos	To obtain a Kerberos ticket
JSON-RPC calls to the IdM Apache- based web-service on discovered or configured IdM servers	HTTPS	IdM client enrollment; retrieval of CA certificate chain if LDAP method fails; request for a certificate issuance if required
Requests over TCP/TCP6 to ports 389 on IdM servers, using SASL GSSAPI authentication, plain LDAP, or both	LDAP	IdM client enrollment; identity retrieval by SSSD processes; Kerberos key retrieval for the host principal
Network time protocol (NTP) discovery and resolution (optionally)	NTP	To synchronize time between the client system and an NTP server

11.8. IDM CLIENT'S COMMUNICATIONS WITH THE SERVER DURING POST-INSTALLATION DEPLOYMENT

The client side of Identity Management (IdM) framework is implemented with two different applications:

- the **ipa** command-line interface (CLI)
- the browser-based Web UI

The browser-based Web UI is optional.

CLI post-installation operations shows the operations performed by the CLI during an IdM client post-installation deployment. Web UI post-installation operations shows the operations performed by the Web UI during an IdM client post-installation deployment.

Two daemons run on the IdM client, the **System Security Services Daemon** (SSSD) and **certmonger**. SSSD communication patterns and Certmonger communication patterns describe how these daemons communicate with the services available on the IdM and Active Directory servers.

Table 11.2. CLI post-installation operations

Operation	Protocol used	Purpose
DNS resolution against the DNS resolvers configured on the client system	DNS	To discover the IP addresses of IdM servers

Operation	Protocol used	Purpose
Requests to ports 88 (TCP/TCP6 and UDP/UDP6) and 464 (TCP/TCP6 and UDP/UDP6) on an IdM replica	Kerberos	To obtain a Kerberos ticket; change a Kerberos password; authenticate to the IdM Web UI
JSON-RPC calls to the IdM Apache- based web-service on discovered or configured IdM servers	HTTPS	any ipa utility usage

Table 11.3. Web UI post-installation operations

Operation	Protocol used	Purpose
JSON-RPC calls to the IdM Apache- based web-service on discovered or configured IdM servers	HTTPS	To retrieve the IdM Web UI pages

11.8.1. SSSD communication patterns

The System Security Services Daemon (SSSD) is a system service to access remote directories and authentication mechanisms. If configured on an Identity Management IdM client, it connects to the IdM server, which provides authentication, authorization and other identity and policy information. If the IdM server is in a trust relationships with Active Directory (AD), SSSD also connects to AD to perform authentication for AD users using the Kerberos protocol. By default, SSSD uses Kerberos to authenticate any non-local user. In special situations, SSSD might be configured to use the LDAP protocol instead.

The SSSD can be configured to communicate with multiple servers. Communication patterns of SSSD on IdM clients when talking to IdM servers and Communication patterns of SSSD on IdM servers acting as trust agents when talking to Active Directory Domain Controllers show common communication patterns for SSSD in IdM.

Table 11.4. Communication patterns of SSSD on IdM clients when talking to IdM servers

Operation	Protocol used	Purpose
DNS resolution against the DNS resolvers configured on the client system	DNS	To discover the IP addresses of IdM servers
Requests to ports 88 (TCP/TCP6 and UDP/UDP6), 464 (TCP/TCP6 and UDP/UDP6), and 749 (TCP/TCP6) on an Identity Management replica and Active Directory domain controllers	Kerberos	To obtain a Kerberos ticket; to change a Kerberos password

Operation	Protocol used	Purpose
Requests over TCP/TCP6 to ports 389 on IdM servers, using SASL GSSAPI authentication, plain LDAP, or both	LDAP	To obtain information about IdM users and hosts, download HBAC and sudo rules, automount maps, the SELinux user context, public SSH keys, and other information stored in IdM LDAP
(optionally) In case of smart-card authentication, requests to the Online Certificate Status Protocol (OCSP) responder, if it is configured. This often is done via port 80, but it depends on the actual value of the OCSP responder URL in a client certificate.	HTTP	To obtain information about the status of the certificate installed in the smart card

Table 11.5. Communication patterns of SSSD on IdM servers acting as trust agents when talking to Active Directory Domain Controllers

Operation	Protocol used	Purpose
DNS resolution against the DNS resolvers configured on the client system	DNS	To discover the IP addresses of IdM servers
Requests to ports 88 (TCP/TCP6 and UDP/UDP6), 464 (TCP/TCP6 and UDP/UDP6), and 749 (TCP/TCP6) on an Identity Management replica and Active Directory domain controllers	Kerberos	To obtain a Kerberos ticket; change a Kerberos password; administer Kerberos remotely
Requests to ports 389 (TCP/TCP6 and UDP/UDP6) and 3268 (TCP/TCP6)	LDAP	To query Active Directory user and group information; to discover Active Directory domain controllers
(optionally) In case of smart-card authentication, requests to the Online Certificate Status Protocol (OCSP) responder, if it is configured. This often is done via port 80, but it depends on the actual value of the OCSP responder URL in a client certificate.	НТТР	To obtain information about the status of the certificate installed in the smart card

11.8.2. Certmonger communication patterns

Certmonger is a daemon running on Identity Management (IdM) servers and IdM clients to allow a timely renewal of SSL certificates associated with the services on the host. The Table 11.6, "Certmonger communication patterns" shows the operations performed by IdM client's **certmonger** utility on IdM servers.

Table 11.6. Certmonger communication patterns

Operation	Protocol used	Purpose
DNS resolution against the DNS resolvers configured on the client system	DNS	To discover the IP addresses of IdM servers
Requests to ports 88 (TCP/TCP6 and UDP/UDP6) and 464 (TCP/TCP6 and UDP/UDP6) on an IdM replica	Kerberos	To obtain a Kerberos ticket
JSON-RPC calls to the IdM Apache- based web-service on discovered or configured IdM servers	HTTPS	To request new certificates
Access over port 8080 (TCP/TCP6) on the IdM server	НТТР	To obtain an Online Certificate Status Protocol (OCSP) responder and certificate status
(on the first installed server or on the server where certificate tracking has been transferred) Access over port 8443 (TCP/TCP6) on the IdM server	HTTPS	To administer the Certificate Authority on the IdM server (only during IdM server and replica installation)

CHAPTER 12. INSTALLING AN IDM CLIENT WITH KICKSTART

A Kickstart enrollment automatically adds a new system to the Identity Management (IdM) domain at the time Red Hat Enterprise Linux is installed.

12.1. INSTALLING A CLIENT WITH KICKSTART

This procedure describes how to use a Kickstart file to install an Identity Management (IdM) client.

Prerequisites

• Do not start the **sshd** service prior to the kickstart enrollment. Starting **sshd** before enrolling the client generates the SSH keys automatically, but the Kickstart file in Section 12.2, "Kickstart file for client installation" uses a script for the same purpose, which is the preferred solution.

Procedure

1. Pre-create the host entry on the IdM server, and set a temporary password for the entry:

\$ ipa host-add client.example.com --password=secret

The password is used by Kickstart to authenticate during the client installation and expires after the first authentication attempt. After the client is successfully installed, it authenticates using its keytab.

- 2. Create a Kickstart file with the contents described in Section 12.2, "Kickstart file for client installation". Make sure that network is configured properly in the Kickstart file using the **network** command.
- 3. Use the Kickstart file to install the IdM client.

12.2. KICKSTART FILE FOR CLIENT INSTALLATION

This section describes the contents of a kickstart file that you can use to install an Identity Management (IdM) client.

The ipa-client package in the list of packages to install

Add the ipa-client package to the %packages section of the kickstart file. For example:

%packages ... ipa-client ...

Post-installation instructions for the IdM client

The post-installation instructions must include:

- An instruction for ensuring SSH keys are generated before enrollment
- An instruction to run the **ipa-client-install** utility, while specifying:
 - All the required information to access and configure the IdM domain services

• The password which you set when pre-creating the client host on the IdM server. in Section 12.1, "Installing a client with Kickstart".

For example, the post-installation instructions for a kickstart installation that uses a one-time password and retrieves the required options from the command line rather than via DNS can look like this:

%post --log=/root/ks-post.log

Generate SSH keys; ipa-client-install uploads them to the IdM server by default /usr/libexec/openssh/sshd-keygen rsa

Run the client install script /usr/sbin/ipa-client-install --hostname=client.example.com --domain=EXAMPLE.COM --enabledns-updates --mkhomedir -w secret --realm=EXAMPLE.COM --server=server.example.com

Optionally, you can also include other options in the Kickstart file, such as:

- For a non-interactive installation, add the **--unattended** option to **ipa-client-install**.
- To let the client installation script request a certificate for the machine:
 - Add the --request-cert option to ipa-client-install.
 - Set the system bus address to /dev/null for both the getcert and ipa-client-install utility in the Kickstart chroot environment. To do this, add these lines to the post-installation instructions in the Kickstart file before the ipa-client-install instruction:

env DBUS_SYSTEM_BUS_ADDRESS=unix:path=/dev/null getcert list # env DBUS_SYSTEM_BUS_ADDRESS=unix:path=/dev/null ipa-client-install

12.3. TESTING AN IDM CLIENT

The command-line interface informs you that the **ipa-client-install** was successful, but you can also do your own test.

To test that the Identity Management (IdM) client can obtain information about users defined on the server, check that you are able to resolve a user defined on the server. For example, to check the default **admin** user:

[user@client ~]\$ **id admin** uid=1254400000(admin) gid=1254400000(admins) groups=1254400000(admins)

To test that authentication works correctly, ${\bf su}$ to a root user from a non-root user:

[user@client ~]\$ **su -**Last login: Thu Oct 18 18:39:11 CEST 2018 from 192.168.122.1 on pts/0 [root@client ~]#

CHAPTER 13. TROUBLESHOOTING IDM CLIENT INSTALLATION

The following sections describe how to gather information about a failing IdM client installation, and how to resolve common installation issues.

- Reviewing IdM client installation errors
- Resolving failing to update IdM DNS records
- Resolving failing to join the IdM Kerberos realm

13.1. REVIEWING IDM CLIENT INSTALLATION ERRORS

When you install an Identity Management (IdM) client, debugging information is appended to /var/log/ipaclient-install.log. If a client installation fails, the installer logs the failure and rolls back changes to undo any modifications to the host. The reason for the installation failure may not be at the end of the log file, as the installer also logs the roll back procedure.

To troubleshoot a failing IdM client installation, review lines labeled **ScriptError** in the /var/log/ipaclient-install.log file and use this information to resolve any corresponding issues.

Prerequisites

• You must have **root** privileges to display the contents of IdM log files.

Procedure

1. Use the **grep** utility to retrieve any occurrences of the keyword **ScriptError** from the /var/log/ipaserver-install.log file.

[user@server ~]\$ sudo grep ScriptError /var/log/ipaclient-install.log [sudo] password for user: 2020-05-28T18:24:50Z DEBUG The ipa-client-install command failed, exception: ScriptError: One of password / principal / keytab is required.

2. To review a log file interactively, open the end of the log file using the **less** utility and use the ↑ and ↓ arrow keys to navigate.

[user@server ~]\$ sudo less -N +G /var/log/ipaclient-install.log

Additional resources

- If you are unable to resolve a failing IdM client installation, and you have a Red Hat Technical Support subscription, open a Technical Support case at the Red Hat Customer Portal and provide an **sosreport** of the client.
- The sosreport utility collects configuration details, logs and system information from a RHEL system. For more information on the sosreport utility, see What is an sosreport and how to create one in Red Hat Enterprise Linux?.

13.2. RESOLVING ISSUES IF THE CLIENT INSTALLATION FAILS TO UPDATE DNS RECORDS

The IdM client installer issues **nsupdate** commands to create PTR, SSHFP, and additional DNS records. However, the installation process fails if the client is unable to update DNS records after installing and configuring the client software.

To fix this problem, verify the configuration and review DNS errors in /var/log/client-install.log.

Prerequisites

• You are using IdM DNS as the DNS solution for your IdM environment

Procedure

1. Ensure that dynamic updates for the DNS zone the client is in are enabled:

[user@server ~]\$ ipa dnszone-mod idm.example.com. --dynamic-update=TRUE

2. Ensure that the IdM server running the DNS service has port 53 opened for both TCP and UDP protocols.

[user@server ~]\$ sudo firewall-cmd --permanent --add-port=53/tcp --add-port=53/udp [sudo] password for user: success [user@server ~]\$ firewall-cmd --runtime-to-permanent

success

3. Use the **grep** utility to retrieve the contents of **nsupdate** commands from /var/log/client-install.log to see which DNS record updates are failing.

[user@server ~]\$ sudo grep nsupdate /var/log/ipaclient-install.log

Additional resources

- If you are unable to resolve a failing installation, and you have a Red Hat Technical Support subscription, open a Technical Support case at the Red Hat Customer Portal and provide an **sosreport** of the client.
- The sosreport utility collects configuration details, logs and system information from a RHEL system. For more information on the sosreport utility, see What is an sosreport and how to create one in Red Hat Enterprise Linux?.

13.3. RESOLVING ISSUES IF THE CLIENT INSTALLATION FAILS TO JOIN THE IDM KERBEROS REALM

The IdM client installation process fails if the client is unable to join the IdM Kerberos realm.

Joining realm failed: Failed to add key to the keytab child exited with 11

Installation failed. Rolling back changes.

This failure can be caused by an empty Kerberos keytab.

Prerequisites

• Removing system files requires **root** privileges.

Procedure

1. Remove /etc/krb5.keytab.

[user@client ~]\$ sudo rm /etc/krb5.keytab [sudo] password for user: [user@client ~]\$ ls /etc/krb5.keytab ls: cannot access '/etc/krb5.keytab': No such file or directory

2. Retry the IdM client installation.

Additional resources

- If you are unable to resolve a failing installation, and you have a Red Hat Technical Support subscription, open a Technical Support case at the Red Hat Customer Portal and provide an **sosreport** of the client.
- The sosreport utility collects configuration details, logs and system information from a RHEL system. For more information on the sosreport utility, see What is an sosreport and how to create one in Red Hat Enterprise Linux?.

13.4. ADDITIONAL RESOURCES

- To troubleshoot installing the first IdM server, see Troubleshooting IdM server installation.
- To troubleshoot installing an IdM replica, see Troubleshooting IdM replica installation .

CHAPTER 14. RE-ENROLLING AN IDM CLIENT

14.1. CLIENT RE-ENROLLMENT IN IDM

This section describes how to re-enroll an Identity Management (IdM) client.

If a client machine has been destroyed and lost connection with the IdM servers, for example due to the client's hardware failure, and you still have its keytab, you can re-enroll the client. In this scenario, you want to get the client back in the IdM environment with the same hostname.

During the re-enrollment, the client generates a new Kerberos key and SSH keys, but the identity of the client in the LDAP database remains unchanged. After the re-enrollment, the host has its keys and other information in the same LDAP object with the same **FQDN** as previously, before the machine's loss of connection with the IdM servers.



IMPORTANT

You can only re-enroll clients whose domain entry is still active. If you uninstalled a client (using **ipa-client-install --uninstall**) or disabled its host entry (using **ipa host-disable**), you cannot re-enroll it.

You cannot re-enroll a client after you have renamed it. This is because in IdM, the key attribute of the client's entry in LDAP is the client's hostname, its **FQDN**. As opposed to re-enrolling a client, during which the client's LDAP object remains unchanged, the outcome of renaming a client is that the client has its keys and other information in a different LDAP object with a new **FQDN**. Thus the only way to rename a client is to uninstall the host from IdM, change the host's hostname, and install it as an IdM client with a new name. For details on how to rename a client, see Chapter 16, *Renaming IdM client systems*.

14.1.1. What happens during client re-enrollment

During re-enrollment, IdM:

- Revokes the original host certificate
- Creates new SSH keys
- Generates a new keytab

14.2. RE-ENROLLING A CLIENT BY USING USER CREDENTIALS: INTERACTIVE RE-ENROLLMENT

This procedure describes re-enrolling an Identity Management (IdM) client interactively by using the credentials of an authorized user.

- 1. Re-create the client machine with the same host name.
- 2. Run the ipa-client-install --force-join command on the client machine:
 - # ipa-client-install --force-join
- 3. The script prompts for a user whose identity will be used to re-enroll the client. This could be, for example, a **hostadmin** user with the Enrollment Administrator role:

User authorized to enroll computers: **hostadmin** Password for **hostadmin@EXAMPLE.COM**:

Additional resources

• For a more detailed procedure on enrolling clients by using an authorized user's credentials, see Section 11.2, "Installing a client by using user credentials: Interactive installation".

14.3. RE-ENROLLING A CLIENT BY USING THE CLIENT KEYTAB: NON-INTERACTIVE RE-ENROLLMENT

Prerequisites

• Back up the original client keytab file, for example in the /tmp or /root directory.

Procedure

This procedure describes re-enrolling an Identity Management (IdM) client non-interactively by using the keytab of the client system. For example, re-enrollment using the client keytab is appropriate for an automated installation.

- 1. Re-create the client machine with the same host name.
- 2. Copy the keytab file from the backup location to the /etc/ directory on the re-created client machine.
- 3. Use the **ipa-client-install** utility to re-enroll the client, and specify the keytab location with the **-keytab** option:

ipa-client-install --keytab /etc/krb5.keytab



NOTE

The keytab specified in the **--keytab** option is only used when authenticating to initiate the enrollment. During the re-enrollment, IdM generates a new keytab for the client.

14.4. TESTING AN IDM CLIENT

The command-line interface informs you that the **ipa-client-install** was successful, but you can also do your own test.

To test that the Identity Management (IdM) client can obtain information about users defined on the server, check that you are able to resolve a user defined on the server. For example, to check the default **admin** user:

[user@client ~]\$ **id admin** uid=1254400000(admin) gid=1254400000(admins) groups=1254400000(admins)

To test that authentication works correctly, **su** to a root user from a non-root user:

[user@client ~]\$ **su -**Last login: Thu Oct 18 18:39:11 CEST 2018 from 192.168.122.1 on pts/0 [root@client ~]#

CHAPTER 15. UNINSTALLING AN IDM CLIENT

As an administrator, you can remove an Identity Management (IdM) client from the environment.

15.1. UNINSTALLING AN IDM CLIENT

Uninstalling a client removes the client from the Identity Management (IdM) domain, along with all of the specific IdM configuration of system services, such as System Security Services Daemon (SSSD). This restores the previous configuration of the client system.

Procedure

1. Enter the ipa-client-install --uninstall command:

[root@client ~]# ipa-client-install --uninstall

2. Optional: Check that you cannot obtain a Kerberos ticket-granting ticket (TGT) for an IdM user:

[root@client ~]# kinit admin kinit: Client 'admin@EXAMPLE.COM' not found in Kerberos database while getting initial credentials [root@client ~]#

If a Kerberos TGT ticket has been returned successfully, follow the additional uninstallation steps in Uninstalling an IdM client: additional steps after multiple past installations .

3. On the client, remove old Kerberos principals from each identified keytab other than /etc/krb5.keytab:

[root@client ~]# ipa-rmkeytab -k /path/to/keytab -r EXAMPLE.COM

4. On an IdM server, remove all DNS entries for the client host from IdM:

[root@server ~]# ipa dnsrecord-del Record name: old-client-name

Zone name: idm.example.com

No option to delete specific record provided.

Delete all? Yes/No (default No): yes

Deleted record "old-client-name"

5. On the IdM server, remove the client host entry from the IdM LDAP server. This removes all services and revokes all certificates issued for that host:

[root@server ~]# ipa host-del client.idm.example.com



IMPORTANT

Removing the client host entry from the IdM LDAP server is crucial if you think you might re-enroll the client in the future, with a different IP address or a different hostname.

15.2. UNINSTALLING AN IDM CLIENT: ADDITIONAL STEPS AFTER MULTIPLE PAST INSTALLATIONS

If you install and uninstall a host as an Identity Management (IdM) client multiple times, the uninstallation procedure might not restore the pre-IdM Kerberos configuration.

In this situation, you must manually remove the IdM Kerberos configuration. In extreme cases, you must reinstall the operating system.

Prerequisites

- You have used the **ipa-client-install --uninstall** command to uninstall the IdM client configuration from the host. However, you can still obtain a Kerberos ticket-granting ticket (TGT) for an IdM user from the IdM server.
- You have checked that the /var/lib/ipa-client/sysrestore directory is empty and hence you
 cannot restore the prior-to-IdM-client configuration of the system using the files in the
 directory.

Procedure

- 1. Check the /etc/krb5.conf.ipa file:
 - If the contents of the /etc/krb5.conf.ipa file are the same as the contents of the krb5.conf file prior to the installation of the IdM client, you can:
 - i. Remove the /etc/krb5.conf file:
 - # rm /etc/krb5.conf
 - ii. Rename the /etc/krb5.conf.ipa file into /etc/krb5.conf:
 - # mv /etc/krb5.conf.ipa /etc/krb5.conf
 - If the contents of the /etc/krb5.conf.ipa file are not the same as the contents of the krb5.conf file prior to the installation of the IdM client, you can at least restore the Kerberos configuration to the state directly after the installation of the operating system:
 - i. Re-install the **krb5-libs** package:
 - # yum reinstall krb5-libs

As a dependency, this command will also re-install the **krb5-workstation** package and the original version of the /etc/krb5.conf file.

2. Remove the **var/log/ipaclient-install.log** file if present.

Verification steps

• Try to obtain IdM user credentials. This should fail:

[root@r8server ~]# kinit admin kinit: Client 'admin@EXAMPLE.COM' not found in Kerberos database while getting initial credentials [root@r8server ~]#

The /etc/krb5.conf file is now restored to its factory state. As a result, you cannot obtain a Kerberos TGT for an IdM user on the host.

CHAPTER 16. RENAMING IDM CLIENT SYSTEMS

The following sections describe how to change the host name of an Identity Management (IdM) client system.



WARNING

Renaming a client is a manual procedure. Do not perform it unless changing the host name is absolutely required.

Renaming an IdM client involves:

- 1. Preparing the host. For details, see Section 16.1, "Prerequisites"
- 2. Uninstalling the IdM client from the host. For details, see Section 16.2, "Uninstalling an IdM client"
- 3. Renaming the host. For details, see Section 16.4, "Renaming the host system"
- 4. Installing the IdM client on the host with the new name. For details, see Section 16.5, "Reinstalling an IdM client"
- 5. Configuring the host after the IdM client installation. For details, see Section 16.6, "Re-adding services, re-generating certificates, and re-adding host groups"

16.1. PREREQUISITES

Before uninstalling the current client, make note of certain settings for the client. You will apply this configuration after re-enrolling the machine with a new host name.

- Identify which services are running on the machine:
 - Use the **ipa service-find** command, and identify services with certificates in the output:
 - \$ ipa service-find old-client-name.example.com
 - In addition, each host has a default host service which does not appear in the ipa service-find output. The service principal for the host service, also called a host principal, is host/old-client-name.example.com.
- For all service principals displayed by ipa service-find old-client-name.example.com, determine the location of the corresponding keytabs on the old-client-name.example.com system:
 - # find / -name "*.keytab"

Each service on the client system has a Kerberos principal in the form service_name/host_name@REALM, such as Idap/old-client-name.example.com@EXAMPLE.COM.

Identify all host groups to which the machine belongs.

ipa hostgroup-find old-client-name.example.com

16.2. UNINSTALLING AN IDM CLIENT

Uninstalling a client removes the client from the Identity Management (IdM) domain, along with all of the specific IdM configuration of system services, such as System Security Services Daemon (SSSD). This restores the previous configuration of the client system.

Procedure

1. Enter the ipa-client-install --uninstall command:

[root@client ~]# ipa-client-install --uninstall

2. Optional: Check that you cannot obtain a Kerberos ticket-granting ticket (TGT) for an IdM user:

[root@client ~]# kinit admin kinit: Client 'admin@EXAMPLE.COM' not found in Kerberos database while getting initial credentials [root@client ~]#

If a Kerberos TGT ticket has been returned successfully, follow the additional uninstallation steps in Uninstalling an IdM client: additional steps after multiple past installations .

3. On the client, remove old Kerberos principals from each identified keytab other than /etc/krb5.keytab:

[root@client ~]# ipa-rmkeytab -k /path/to/keytab -r EXAMPLE.COM

4. On an IdM server, remove all DNS entries for the client host from IdM:

[root@server ~]# ipa dnsrecord-del Record name: old-client-name Zone name: idm.example.com

No option to delete specific record provided.

Delete all? Yes/No (default No): yes

Deleted record "old-client-name"

5. On the IdM server, remove the client host entry from the IdM LDAP server. This removes all services and revokes all certificates issued for that host:

[root@server ~]# ipa host-del client.idm.example.com



IMPORTANT

Removing the client host entry from the IdM LDAP server is crucial if you think you might re-enroll the client in the future, with a different IP address or a different hostname.

16.3. UNINSTALLING AN IDM CLIENT: ADDITIONAL STEPS AFTER MULTIPLE PAST INSTALLATIONS

If you install and uninstall a host as an Identity Management (IdM) client multiple times, the uninstallation procedure might not restore the pre-IdM Kerberos configuration.

In this situation, you must manually remove the IdM Kerberos configuration. In extreme cases, you must reinstall the operating system.

Prerequisites

- You have used the **ipa-client-install --uninstall** command to uninstall the IdM client configuration from the host. However, you can still obtain a Kerberos ticket-granting ticket (TGT) for an IdM user from the IdM server.
- You have checked that the /var/lib/ipa-client/sysrestore directory is empty and hence you
 cannot restore the prior-to-IdM-client configuration of the system using the files in the
 directory.

Procedure

- 1. Check the /etc/krb5.conf.ipa file:
 - If the contents of the /etc/krb5.conf.ipa file are the same as the contents of the krb5.conf file prior to the installation of the IdM client, you can:
 - i. Remove the /etc/krb5.conf file:
 - # rm /etc/krb5.conf
 - ii. Rename the /etc/krb5.conf.ipa file into /etc/krb5.conf:
 - # mv /etc/krb5.conf.ipa /etc/krb5.conf
 - If the contents of the /etc/krb5.conf.ipa file are not the same as the contents of the krb5.conf file prior to the installation of the IdM client, you can at least restore the Kerberos configuration to the state directly after the installation of the operating system:
 - i. Re-install the **krb5-libs** package:
 - # yum reinstall krb5-libs

As a dependency, this command will also re-install the **krb5-workstation** package and the original version of the **/etc/krb5.conf** file.

2. Remove the **var/log/ipaclient-install.log** file if present.

Verification steps

• Try to obtain IdM user credentials. This should fail:

[root@r8server ~]# kinit admin kinit: Client 'admin@EXAMPLE.COM' not found in Kerberos database while getting initial credentials [root@r8server ~]#

The /etc/krb5.conf file is now restored to its factory state. As a result, you cannot obtain a Kerberos TGT for an IdM user on the host.

16.4. RENAMING THE HOST SYSTEM

Rename the machine as required. For example:

hostnamectl set-hostname new-client-name.example.com

You can now re-install the Identity Management (IdM) client to the IdM domain with the new host name.

16.5. RE-INSTALLING AN IDM CLIENT

Install an client on your renamed host following the procedure described in Chapter 11, *Installing an IdM client: Basic scenario*.

16.6. RE-ADDING SERVICES, RE-GENERATING CERTIFICATES, AND RE-ADDING HOST GROUPS

- 1. On the Identity Management (IdM) server, add a new keytab for every service identified in Section 16.1, "Prerequisites".
 - [root@server ~]# ipa service-add service_name/new-client-name
- 2. Generate certificates for services that had a certificate assigned in Section 16.1, "Prerequisites". You can do this:
 - Using the IdM administration tools
 - Using the certmonger utility
- 3. Re-add the client to the host groups identified in Section 16.1, "Prerequisites".

CHAPTER 17. PREPARING THE SYSTEM FOR IDM REPLICA INSTALLATION

The following links list the requirements to install an Identity Management (IdM) replica. Before the installation, make sure your system meets these requirements.

- 1. Ensure the target system meets the general requirements for IdM server installation.
- 2. Ensure the target system meets the additional requirements for IdM replica installation .
- 3. Authorize the target system for enrollment into the IdM domain. For more information, see one of the following sections that best fits your needs:
 - Section 17.3, "Authorizing the installation of a replica on an IdM client"
 - Section 17.4, "Authorizing the installation of a replica on a system that is not enrolled into IdM"

17.1. REPLICA VERSION REQUIREMENTS

Red Hat Enterprise Linux (RHEL) 8 replicas only work with Identity Management (IdM) servers running on RHEL 7.4 and later. Before introducing IdM replicas running on RHEL 8 into an existing deployment, upgrade all IdM servers to RHEL 7.4 or later, and change the domain level to 1.

In addition, the replica must be running the same or later version of IdM. For example:

- You have an IdM server installed on Red Hat Enterprise Linux 8 and it uses IdM 4.x packages.
- You must install the replica also on Red Hat Enterprise Linux 8 or later and use IdM version 4.x or later.

This ensures that configuration can be properly copied from the server to the replica.

For details on how to display the IdM software version, see Section 17.2, "Methods for displaying IdM software version".


17.2. METHODS FOR DISPLAYING IDM SOFTWARE VERSION

You can display the IdM version number with:

- the IdM WebUI
- **ipa** commands
- rpm commands

Displaying version through the WebUI

In the IdM WebUI, the software version can be displayed by choosing **About** from the username menu at the top-right.



Displaying version with ipa commands

From the command line, use the **ipa --version** command.

[root@server ~]# ipa --version

VERSION: 4.8.0, API_VERSION: 2.233

Displaying version with rpm commands

If IdM services are not operating properly, you can use the **rpm** utility to determine the version number of the **ipa-server** package that is currently installed.

[root@server ~]# rpm -q ipa-server ipa-server-4.8.0-11.module+el8.1.0+4247+9f3fd721.x86_64

17.3. AUTHORIZING THE INSTALLATION OF A REPLICA ON AN IDM CLIENT

When installing a replica on an existing Identity Management (IdM) client by running the **ipa-replica-install** utility, choose **Method 1** or **Method 2** below to authorize the replica installation. Choose **Method 1** if one of the following applies:

- You want a senior system administrator to perform the initial part of the procedure and a junior administrator to perform the rest.
- You want to automate your replica installation.

Method 1: the ipaservers host group

1. Log in to any IdM host as IdM admin:

\$ kinit admin

2. Add the client machine to the **ipaservers** host group:

\$ ipa hostgroup-add-member ipaservers --hosts client.idm.example.com

Host-group: ipaservers Description: IPA server hosts Member hosts: server.idm.example.com, client.idm.example.com

Number of members added 1



NOTE

Membership in the **ipaservers** group grants the machine elevated privileges similar to the administrator's credentials. Therefore, in the next step, the **ipa-replica-install** utility can be run on the host successfully by a junior system administrator.

Method 2: a privileged user's credentials

Choose one of the following methods to authorize the replica installation by providing a privileged user's credentials:

- Let Identity Management (IdM) prompt you for the credentials interactively after you start the **ipa-replica-install** utility. This is the default behavior.
- Log in to the client as a privileged user immediately before running the **ipa-replica-install** utility. The default privileged user is **admin**:

\$ kinit admin

Additional resources

- To start the installation procedure, see Installing an IdM replica .
- You can use an Ansible playbook to install IdM replicas. For more information, see Installing an Identity Management replica using an Ansible playbook.

17.4. AUTHORIZING THE INSTALLATION OF A REPLICA ON A SYSTEM THAT IS NOT ENROLLED INTO IDM

When installing a replica on a system that is not enrolled in the Identity Management (IdM) domain, the **ipa-replica-install** utility first enrolls the system as a client and then installs the replica components. For this scenario, choose **Method 1** or **Method 2** below to authorize the replica installation. Choose **Method 1** if one of the following applies:

- You want a senior system administrator to perform the initial part of the procedure and a junior administrator to perform the rest.
- You want to automate your replica installation.

Method 1: a random password generated on an IdM server

Enter the following commands on any server in the domain:

1. Log in as the administrator.

\$ kinit admin

2. Add the external system as an IdM host. Use the **--random** option with the **ipa host-add** command to generate a random one-time password to be used for the subsequent replica installation.

\$ ipa host-add replica.example.com --random

Added host "replica.example.com"

Host name: replica.example.com Random password: W5YpARI=7M.n

Password: True Keytab: False

Managed by: server.example.com

The generated password will become invalid after you use it to enroll the machine into the IdM domain. It will be replaced with a proper host keytab after the enrollment is finished.

3. Add the system to the **ipaservers** host group.

\$ ipa hostgroup-add-member ipaservers --hosts replica.example.com

Host-group: ipaservers

Description: IPA server hosts

Member hosts: server.example.com, replica.example.com

Number of members added 1



NOTE

Membership in the **ipaservers** group grants the machine elevated privileges similar to the administrator's credentials. Therefore, in the next step, the **ipa-replica-install** utility can be run on the host successfully by a junior system administrator that provides the generated random password.

Method 2: a privileged user's credentials

Using this method, you authorize the replica installation by providing a privileged user's credentials. The default privileged user is **admin**.

No action is required prior to running the IdM replica installation utility. Add the principal name and password options (--principal admin --admin-password password) to the ipa-replica-install command directly during the installation.

Additional resources

- To start the installation procedure, see Installing an IdM replica .
- You can use an Ansible playbook to install IdM replicas. For more information, see Installing an Identity Management replica using an Ansible playbook.

CHAPTER 18. INSTALLING AN IDM REPLICA

The following sections describe how to install an Identity Management (IdM) replica. The replica installation process copies the configuration of the existing server and installs the replica based on that configuration.

Prerequisites

Ensure your system is prepared for IdM replica installation.



IMPORTANT

If this preparation is not performed, installing an IdM replica will fail.



NOTE

Install one IdM replica at a time. The installation of multiple replicas at the same time is not supported.

Procedure

For the individual types of replica installation procedures, see:

- Section 18.1, "Installing an IdM replica with integrated DNS and a CA"
- Section 18.2, "Installing an IdM replica with integrated DNS"
- Section 18.3, "Installing an IdM replica with a CA"
- Section 18.4, "Installing an IdM replica without a CA"
- Section 18.5, "Installing an IdM hidden replica"

To troubleshoot the replica installation procedure, see:

• Chapter 19, Troubleshooting IdM replica installation

After the installation, see:

Section 18.6, "Testing an IdM replica"

18.1. INSTALLING AN IDM REPLICA WITH INTEGRATED DNS AND A CA

This procedure describes installing an Identity Management (IdM) replica:

- With integrated DNS
- With a certificate authority (CA)

You can do this to, for example, replicate the CA service for resiliency after installing an IdM server with an integrated CA.



IMPORTANT

When configuring a replica with a CA, the CA configuration of the replica must mirror the CA configuration of the other server.

For example, if the server includes an integrated IdM CA as the root CA, the new replica must also be installed with an integrated CA as the root CA. No other CA configuration is available in this case.

Including the **--setup-ca** option in the **ipa-replica-install** command copies the CA configuration of the initial server.

Prerequisites

• Ensure your system is prepared for an IdM replica installation .

Procedure

- 1. Enter ipa-replica-install with these options:
 - --setup-dns to configure the replica as a DNS server
 - --forwarder to specify a forwarder, or --no-forwarder if you do not want to use any
 forwarders. To specify multiple forwarders for failover reasons, use --forwarder multiple
 times.
 - --setup-ca to include a CA on the replica
 For example, to set up a replica with an integrated DNS server and a CA that forwards all DNS requests not managed by the IdM servers to the DNS server running on IP 192.0.2.1:
 - # ipa-replica-install --setup-dns --forwarder 192.0.2.1 --setup-ca



NOTE

The **ipa-replica-install** utility accepts a number of other options related to DNS settings, such as **--no-reverse** or **--no-host-dns**. For more information about them, see the **ipa-replica-install**(1) man page.

2. After the installation completes, add a DNS delegation from the parent domain to the IdM DNS domain. For example, if the IdM DNS domain is **idm.example.com**, add a name server (NS) record to the **example.com** parent domain.



IMPORTANT

Repeat this step each time after you installed an IdM DNS server.

18.2. INSTALLING AN IDM REPLICA WITH INTEGRATED DNS

This procedure describes installing an Identity Management (IdM) replica:

- With integrated DNS
- Without a certificate authority (CA) in an IdM environment in which a CA is already installed. The
 replica will forward all certificate operations to the IdM server with a CA installed.

Prerequisites

• Ensure your system is prepared for an IdM replica installation .

Procedure

- 1. Enter **ipa-replica-install** with these options:
 - --setup-dns to configure the replica as a DNS server
 - **--forwarder** to specify a forwarder, or **--no-forwarder** if you do not want to use any forwarders. To specify multiple forwarders for failover reasons, use **--forwarder** multiple times.

For example, to set up a replica with an integrated DNS server that forwards all DNS requests not managed by the IdM servers to the DNS server running on IP 192.0.2.1:

ipa-replica-install --setup-dns --forwarder 192.0.2.1



NOTE

The **ipa-replica-install** utility accepts a number of other options related to DNS settings, such as **--no-reverse** or **--no-host-dns**. For more information about them, see the **ipa-replica-install**(1) man page.

2. After the installation completes, add a DNS delegation from the parent domain to the IdM DNS domain. For example, if the IdM DNS domain is **idm.example.com**, add a name server (NS) record to the **example.com** parent domain.



IMPORTANT

Repeat this step each time after you installed an IdM DNS server.

18.3. INSTALLING AN IDM REPLICA WITH A CA

This procedure describes installing an Identity Management (IdM) replica:

- Without integrated DNS
- With a certificate authority (CA)



IMPORTANT

When configuring a replica with a CA, the CA configuration of the replica must mirror the CA configuration of the other server.

For example, if the server includes an integrated IdM CA as the root CA, the new replica must also be installed with an integrated CA as the root CA. No other CA configuration is available in this case.

Including the **--setup-ca** option in the **ipa-replica-install** command copies the CA configuration of the initial server.

Prerequisites

Ensure your system is prepared for an IdM replica installation.

Procedure

- 1. Enter **ipa-replica-install** with the **--setup-ca** option.
 - # ipa-replica-install --setup-ca
- 2. Add the newly created IdM DNS service records to your DNS server:
 - a. Export the IdM DNS service records into a file in the **nsupdate** format:
 - \$ ipa dns-update-system-records --dry-run --out dns_records_file.nsupdate
 - b. Submit a DNS update request to your DNS server using the **nsupdate** utility and the **dns_records_file.nsupdate** file. For more information, see Updating External DNS Records Using nsupdate in RHEL 7 documentation. Alternatively, refer to your DNS server documentation for adding DNS records.

18.4. INSTALLING AN IDM REPLICA WITHOUT A CA

This procedure describes installing an Identity Management (IdM) replica:

- Without integrated DNS
- Without a certificate authority (CA) by providing the required certificates manually. The
 assumption here is that the first server was installed without a CA.



IMPORTANT

You cannot install a server or replica using self-signed third-party server certificates because the imported certificate files must contain the full CA certificate chain of the CA that issued the LDAP and Apache server certificates.

Prerequisites

• Ensure your system is prepared for an IdM replica installation .

Procedure

- Enter **ipa-replica-install**, and provide the required certificate files by adding these options:
 - o --dirsrv-cert-file
 - --dirsrv-pin
 - o --http-cert-file
 - o --http-pin

For details about the files that are provided using these options, see Section 4.1, "Certificates required to install an IdM server without a CA".

For example:

ipa-replica-install \

- --dirsrv-cert-file /tmp/server.crt \
- --dirsrv-cert-file /tmp/server.key \
- --dirsrv-pin secret \
- --http-cert-file /tmp/server.crt \
- --http-cert-file /tmp/server.key \
- --http-pin secret



NOTE

Do not add the **--ca-cert-file** option. The **ipa-replica-install** utility takes this part of the certificate information automatically from the first server you installed.

18.5. INSTALLING AN IDM HIDDEN REPLICA

A hidden (unadvertised) replica is an Identity Management (IdM) server that has all services running and available. However, it has no SRV records in DNS, and LDAP server roles are not enabled. Therefore, clients cannot use service discovery to detect these hidden replicas.

For further details about hidden replicas, see The hidden replica mode.

Prerequisites

• Ensure your system is prepared for an IdM replica installation .

Procedure

• To install a hidden replica, use the following command:

ipa-replica-install --hidden-replica

Note that the command installs a replica without DNS SRV records and with disabled LDAP server roles.

You can also change the mode of existing replica to hidden. For details, see Demotion and promotion of hidden replicas.

18.6. TESTING AN IDM REPLICA

After creating a replica, check if the replica replicates data as expected. You can use the following procedure.

Procedure

- 1. Create a user on the new replica:
 - [admin@new_replica ~]\$ ipa user-add test_user
- 2. Make sure the user is visible on another replica:

[admin@another_replica ~]\$ ipa user-show test_user

18.7. CONNECTIONS PERFORMED DURING AN IDM REPLICA INSTALLATION

Table 18.1, "Requests performed during an IdM replica installation" lists the operations performed by **ipa-replica-install**, the Identity Management (IdM) replica installation tool.

Table 18.1. Requests performed during an IdM replica installation

Operation	Protocol used	Purpose
DNS resolution against the DNS resolvers configured on the client system	DNS	To discover the IP addresses of IdM servers
Requests to ports 88 (TCP/TCP6 and UDP/UDP6) on the discovered IdM servers	Kerberos	To obtain a Kerberos ticket
JSON-RPC calls to the IdM Apache- based web-service on the discovered or configured IdM servers	HTTPS	IdM client enrollment; replica keys retrieval and certificate issuance if required
Requests over TCP/TCP6 to port 389 on the IdM server, using SASL GSSAPI authentication, plain LDAP, or both	LDAP	IdM client enrollment; CA certificate chain retrieval; LDAP data replication
Requests over TCP/TCP6 to port 22 on IdM server	SSH	To check if the connection is working
(optionally) Access over port 8443 (TCP/TCP6) on the IdM servers	HTTPS	To administer the Certificate Authority on the IdM server (only during IdM server and replica installation)

CHAPTER 19. TROUBLESHOOTING IDM REPLICA INSTALLATION

The following sections describe the process for gathering information about a failing IdM replica installation, and how to resolve some common installation issues.

- Reviewing IdM replica installation errors
- Reviewing IdM CA installation errors
- Removing a partial IdM replica installation
- Resolving invalid credentials

19.1. REVIEWING IDM REPLICA INSTALLATION ERRORS

When you install an Identity Management (IdM) replica, debugging information is appended to the following log files on the replica:

- /var/log/ipareplica-install.log
- /var/log/ipareplica-conncheck.log
- /var/log/ipaclient-install.log
- /var/log/httpd/error_log
- /var/log/dirsrv/slapd-INSTANCE-NAME/access
- /var/log/dirsrv/slapd-INSTANCE-NAME/errors
- /var/log/ipaserver-install.log

The replica installation process also appends debugging information to the following log files on the IdM **server** the replica is contacting:

- /var/log/httpd/error_log
- /var/log/dirsrv/slapd-INSTANCE-NAME/access
- /var/log/dirsrv/slapd-INSTANCE-NAME/errors

The last line of each log file reports success or failure, and **ERROR** and **DEBUG** entries provide additional context.

To troubleshoot a failing IdM replica installation, review the errors at the end of these log files on both hosts (replica and server) and use this information to resolve any corresponding issues.

Prerequisites

• You must have **root** privileges to display the contents of IdM log files.

Procedure

1. Use the **tail** command to display the latest errors from the primary log file /var/log/ipareplica-install.log. The following example displays the last 10 lines.

```
[user@replica ~]$ sudo tail -n 10 /var/log/ipareplica-install.log [sudo] password for user:
```

func(installer)

File "/usr/lib/python3.6/site-packages/ipaserver/install/server/replicainstall.py", line 424, in decorated

func(installer)

File "/usr/lib/python3.6/site-packages/ipaserver/install/server/replicainstall.py", line 785, in promote check

ensure_enrolled(installer)

File "/usr/lib/python3.6/site-packages/ipaserver/install/server/replicainstall.py", line 740, in ensure enrolled

raise ScriptError("Configuration of client side components failed!")

2020-05-28T18:24:51Z **DEBUG The ipa-replica-install command failed, exception:**

ScriptError: Configuration of client side components failed!

2020-05-28T18:24:51Z ERROR Configuration of client side components failed!

2020-05-28T18:24:51Z ERROR The ipa-replica-install command failed. See

/var/log/ipareplica-install.log for more information

2. To review the log file interactively, open the end of the log file using the **less** utility and use the ↑ and ↓ arrow keys to navigate.

[user@replica ~]\$ sudo less -N +G /var/log/ipareplica-install.log

3. (Optional) While /var/log/ipareplica-install.log is the primary log file for a replica installation, you can gather additional troubleshooting information by repeating this review process with additional files on the replica and the server.

On the replica:

```
[user@replica ~]$ sudo less -N +G /var/log/ipareplica-conncheck.log
[user@replica ~]$ sudo less -N +G /var/log/ipaclient-install.log
[user@replica ~]$ sudo less -N +G /var/log/httpd/error_log
[user@replica ~]$ sudo less -N +G /var/log/dirsrv/slapd-INSTANCE-NAME/access
[user@replica ~]$ sudo less -N +G /var/log/dirsrv/slapd-INSTANCE-NAME/errors
[user@replica ~]$ sudo less -N +G /var/log/ipaserver-install.log
```

On the server:

```
[user@server ~]$ sudo less -N +G /var/log/httpd/error_log
[user@server ~]$ sudo less -N +G /var/log/dirsrv/slapd-INSTANCE-NAME/access
[user@server ~]$ sudo less -N +G /var/log/dirsrv/slapd-INSTANCE-NAME/errors
```

Additional resources

• If you are unable to resolve a failing replica installation, and you have a Red Hat Technical Support subscription, open a Technical Support case at the Red Hat Customer Portal and provide an **sosreport** of the replica and an **sosreport** of the server.

• The **sosreport** utility collects configuration details, logs and system information from a RHEL system. For more information on the **sosreport** utility, see What is an sosreport and how to create one in Red Hat Enterprise Linux?.

19.2. REVIEWING IDM CA INSTALLATION ERRORS

Installing the Certificate Authority (CA) service on an Identity Management (IdM) replica appends debugging information to several locations on the replica and the IdM server the replica communicates with.

Table 19.1. On the replica (in order of recommended priority):

Location	Description
/var/log/pki/pki-ca- spawn. <i>\$TIME_OF_INSTALLATION</i> .log	High-level issues and Python traces for the pkispawn installation process
journalctl -u pki-tomcatd@pki-tomcat output	Errors from the pki-tomcatd@pki-tomcat service
/var/log/pki/pki-tomcat/ca/debug.\$DATE.log	Large JAVA stacktraces of activity in the core of the Public Key Infrastructure (PKI) product
/var/log/pki/pki- tomcat/ca/signedAudit/ca_audit	Audit log of the PKI product
 /var/log/pki/pki-tomcat/ca/system /var/log/pki/pki-tomcat/ca/transactions /var/log/pki/pki-tomcat/catalina.\$DATE.log 	Low-level debug data of certificate operations for service principals, hosts, and other entities that use certificates

On the server contacted by the replica:

/var/log/httpd/error_log log file

Installing the CA service on an existing IdM replica also writes debugging information to the following log file:

• /var/log/ipareplica-ca-install.log log file



NOTE

If a full IdM replica installation fails while installing the optional CA component, no details about the CA are logged; a message is logged in the /var/log/ipareplica-install.log file indicating that the overall installation process failed. Red Hat recommends reviewing the log files listed above for details specific to the CA installation failure.

The only exception to this behavior is when you are installing the CA service and the root CA is an external CA. If there is an issue with the certificate from the external CA, errors are logged in /var/log/ipareplica-install.log.

To troubleshoot a failing IdM CA installation, review the errors at the end of these log files and use this information to resolve any corresponding issues.

Prerequisites

• You must have **root** privileges to display the contents of IdM log files.

Procedure

- To review a log file interactively, open the end of the log file using the less utility and use the ↑ and ↓ arrow keys to navigate, while searching for ScriptError entries. The following example opens /var/log/pki/pki-ca-spawn.\$TIME_OF_INSTALLATION.log.
 - [user@server ~]\$ sudo less -N +G /var/log/pki/pki-ca-spawn.20200527185902.log
- 2. Gather additional troubleshooting information by repeating this review process with all the log files listed above.

Additional resources

- If you are unable to resolve a failing installation, and you have a Red Hat Technical Support subscription, open a Technical Support case at the Red Hat Customer Portal and provide an **sosreport** of the replica and an **sosreport** of the server.
- The sosreport utility collects configuration details, logs and system information from a RHEL system. For more information on the sosreport utility, see What is an sosreport and how to create one in Red Hat Enterprise Linux?.

19.3. REMOVING A PARTIAL IDM REPLICA INSTALLATION

If an IdM replica installation fails, some configuration files may be left behind. Additional attempts to install the IdM replica can fail and the installation script reports that IPA is already configured.

[root@server ~]# ipa-replica-install

Your system may be partly configured.

Run /usr/sbin/ipa-server-install --uninstall to clean up.

IPA server is already configured on this system.

If you want to reinstall the IPA server, please uninstall it first using 'ipa-server-install --uninstall'.

The ipa-replica-install command failed. See /var/log/ipareplica-install.log for more information

To resolve this issue, uninstall IdM software from the replica, remove the replica from the IdM topology, and retry the installation process.

Prerequisites

• You must have **root** privileges.

Procedure

1. Uninstall the IdM server software on the host you are trying to configure as an IdM replica.

[root@replica ~]# ipa-server-install --uninstall

2. On all other servers in the topology, use the **ipa server-del** command to delete any references to the replica that did not install properly.

[root@other-replica ~]# ipa server-del replica.idm.example.com

- 3. Attempt installing the replica.
- 4. If you continue to experience difficulty installing an IdM replica because of repeated failed installations, reinstall the operating system.

One of the requirements for installing an IdM replica is a clean system without any customization. Failed installations may have compromised the integrity of the host by unexpectedly modifying system files.

Additional resources

- For additional details on uninstalling an IdM replica, see Uninstalling an IdM replica.
- If installation attempts fail after repeated uninstallation attempts, and you have a Red Hat Technical Support subscription, open a Technical Support case at the Red Hat Customer Portal and provide an **sosreport** of the replica and an **sosreport** of the server.
- The **sosreport** utility collects configuration details, logs and system information from a RHEL system. For more information on the **sosreport** utility, see What is an sosreport and how to create one in Red Hat Enterprise Linux?.

19.4. RESOLVING INVALID CREDENTIAL ERRORS

If an IdM replica installation fails with an **Invalid credentials** error, the system clocks on the hosts may be out of sync with each other:

[27/40]: setting up initial replication

Starting replication, please wait until this has completed.

Update in progress, 15 seconds elapsed

[ldap://server.example.com:389] reports: **Update failed! Status: [49 - LDAP error: Invalid credentials]**

[error] RuntimeError: Failed to start replication

Your system may be partly configured.

Run /usr/sbin/ipa-server-install --uninstall to clean up.

ipa.ipapython.install.cli.install_tool(CompatServerReplicaInstall): ERROR Failed to start replication ipa.ipapython.install.cli.install_tool(CompatServerReplicaInstall): ERROR The ipa-replica-install command failed. See /var/log/ipareplica-install.log for more information

If you use the **--no-ntp** or **-N** options to attempt the replica installation while clocks are out of sync, the installation fails because services are unable to authenticate with Kerberos.

To resolve this issue, synchronize the clocks on both hosts and retry the installation process.

Prerequisites

• You must have **root** privileges to change system time.

Procedure

- 1. Synchronize the system clocks manually or with **chronyd** (**ntp** is no longer supported in RHEL 8).
 - Synchronizing manually:

Display the system time on the server and set the replica's time to match.

[user@server ~]\$ **date** Thu May 28 21:03:57 EDT 2020

[user@replica ~]\$ sudo timedatectl set-time '2020-05-28 21:04:00'

- Synchronizing with chronyd:
 Refer to Using the Chrony suite to configure NTP to configure and set system time with chrony tools.
- 2. Attempt the IdM replica installation again.

Additional resources

- If you are unable to resolve a failing replica installation, and you have a Red Hat Technical Support subscription, open a Technical Support case at the Red Hat Customer Portal and provide an **sosreport** of the replica and an **sosreport** of the server.
- The sosreport utility collects configuration details, logs and system information from a RHEL system. For more information on the sosreport utility, see What is an sosreport and how to create one in Red Hat Enterprise Linux?.

19.5. ADDITIONAL RESOURCES

- To troubleshoot installing the first IdM server, see Troubleshooting IdM server installation.
- To troubleshoot installing an IdM client, see Troubleshooting IdM client installation.

CHAPTER 20. UNINSTALLING AN IDM REPLICA

As an administrator, you can remove an Identity Management (IdM) server from the topology.

This procedure describes how you can uninstall an example server named **server.idm.example.com**.

Prerequisites

• Before uninstalling a server that serves as a certificate authority (CA), key recovery authority (KRA), or DNS server, make sure these services are running on another server in the domain.



WARNING

Removing the last server that serves as a CA, KRA, or DNS server seriously disrupts the Identity Management (IdM) functionality.

Procedure

- 1. On another server, enter the **ipa server-del** command to delete **server.idm.example.com** from the topology:
 - [root@another_server ~]# ipa server-del server.idm.example.com
- 2. On server.idm.example.com, use the ipa-server-install --uninstall command:

[root@server ~]# ipa-server-install --uninstall ...

Are you sure you want to continue with the uninstall procedure? [no]: yes

3. Make sure all name server (NS) DNS records pointing to **server.idm.example.com** are deleted from your DNS zones. This applies regardless of whether you use integrated DNS managed by IdM or external DNS.

CHAPTER 21. INSTALLING AND RUNNING THE IDM HEALTHCHECK TOOL

This chapter describes the IdM Healthcheck tool and how to install and run it.

Prerequisites

• The Healthcheck tool is only available on RHEL 8.1 or later.

21.1. HEALTHCHECK IN IDM

The Healthcheck tool in Identity Management (IdM) helps find issues that may impact the health of your IdM environment.



NOTE

The Healthcheck tool is a command line tool that can be used without Kerberos authentication.

21.1.1. Modules are Independent

Healthcheck consists of independent modules which test for:

- Replication issues
- Certificate validity
- Certificate Authority infrastructure issues
- IdM and Active Directory trust issues
- Correct file permissions and ownership settings

21.1.2. Two output formats

Healthcheck generates the following outputs, which you can set using the **output-type** option:

- **json**: Machine-readable output in JSON format (default)
- human: Human-readable output

You can specify a different file destination with the --output-file option.

21.1.3. Results

Each Healthcheck module returns one of the following results:

SUCCESS

configured as expected

WARNING

not an error, but worth keeping an eye on or evaluating

ERROR

not configured as expected

CRITICAL

not configured as expected, with a high possibility for impact

21.2. INSTALLING IDM HEALTHCHECK

This section describes how to install the IdM Healthcheck tool.

Procedure

• Install the **ipa-healthcheck** package:

[root@server ~]# dnf install ipa-healthcheck



NOTE

On RHEL 8.1 and 8.2 systems, use the **dnf install /usr/bin/ipa-healthcheck** command instead.

Verification steps

• Use the **--failures-only** option to have **ipa-healthcheck** only report errors. A fully-functioning IdM installation returns an empty result of [].

[root@server ~]# ipa-healthcheck --failures-only

Additional resources

• Use **ipa-healthcheck --help** to see all supported arguments.

21.3. RUNNING IDM HEALTHCHECK

Healthcheck can be run manually or automatically using log rotation.

Prerequisites

• The Healthcheck tool must be installed. See Installing IdM Healthcheck.

Procedure

• To run healthcheck manually, enter the **ipa-healthcheck** command.

[root@server ~]# ipa-healthcheck

Additional resources

For all options, see the man page: man ipa-healthcheck.

21.4. ADDITIONAL RESOURCES

- See the following sections of the Configuring and managing Identity Management guide for examples of using IdM Healthcheck.
 - Checking services
 - Verifying your IdM and AD trust configuration
 - Verifying certificates
 - Verifying system certificates
 - Checking disk space
 - Verifying permissions of IdM configuration files
 - Checking replication
- You can also see those chapters organized into a single guide: Using IdM Healthcheck to monitor your IdM environment

CHAPTER 22. INSTALLING AN IDENTITY MANAGEMENT SERVER USING AN ANSIBLE PLAYBOOK

22.1. ANSIBLE AND ITS ADVANTAGES FOR INSTALLING IDM

Ansible is an automation tool used to configure systems, deploy software, and perform rolling updates. Ansible includes support for Identity Management (IdM), and you can use Ansible modules to automate installation tasks such as the setup of an IdM server, replica, client, or an entire IdM topology.

Advantages of using Ansible to install IdM

The following list presents advantages of installing Identity Management using Ansible in contrast to manual installation.

- You do not need to log into the managed node.
- You do not need to configure settings on each host to be deployed individually. Instead, you can have one inventory file to deploy a complete cluster.
- You can reuse an inventory file later for management tasks, for example to add users and hosts. You can reuse an inventory file even for such tasks as are not related to IdM.

22.2. IDM SERVER INSTALLATION USING AN ANSIBLE PLAYBOOK

The following sections describe how to configure a system as an IdM server by using Ansible. Configuring a system as an IdM server establishes an IdM domain and enables the system to offer IdM services to IdM clients. The deployment is managed by the **ipaserver** Ansible role.



NOTE

Before installing an IdM server using Ansible, ensure that you understand Ansible and IdM concepts. Ensure that you understand the following terms that are used in this chapter:

- Ansible roles
- Ansible nodes
- Ansible inventory
- Ansible tasks
- Ansible modules
- Ansible plays and playbooks

Overview

The installation consists of the following parts:

- 1. Installing the ansible-freeipa package
- 2. Deploying an IdM server with an integrated CA using an Ansible playbook
- 3. Deploying an IdM server with an external CA using an Ansible-playbook

22.3. INSTALLING THE ANSIBLE-FREEIPA PACKAGE

Prerequisites

On the managed node:

• Ensure that the managed node is a Red Hat Enterprise Linux 8 system with a static IP address and a working package manager.

On the controller:

- Ensure that the controller is a Red Hat Enterprise Linux system with a valid subscription. If this is not the case, see the official Ansible documentation Installation guide for alternative installation instructions.
- Ensure that you can reach the managed node over the **SSH** protocol from the controller. Check that the managed node is listed in the /**root/.ssh/known_hosts** file of the controller.

Procedure

Run the following procedure on the Ansible controller.

- 1. Enable the required repository:
 - # subscription-manager repos --enable ansible-2.8-for-rhel-8-x86_64-rpms
- 2. Install Ansible:
 - # yum install ansible
- 3. Install the IdM Ansible roles:
 - # yum install ansible-freeipa

The roles are installed to the /usr/share/ansible/roles/ directory.

22.4. ANSIBLE ROLES LOCATION IN THE FILE SYSTEM

By default the **ansible-freeipa** roles are installed to the **/usr/share/ansible/roles/** directory. The structure of the **ansible-freeipa** package is as follows:

• The /usr/share/ansible/roles/ directory stores the ipaserver, ipareplica, and ipaclient roles on the Ansible controller. Each role directory stores examples, a basic overview, the licence and documentation about the role in a README.md Markdown file.

[root@server]# **Is -1** /**usr/share/ansible/roles/** ipaclient ipareplica ipaserver

 The /usr/share/doc/ansible-freeipa/ directory stores the documentation about individual roles and the topology in README.md Markdown files. It also stores the playbooks/ subdirectory (see below).

[root@server]# Is -1 /usr/share/doc/ansible-freeipa/

playbooks
README-client.md
README.md
README-replica.md
README-server.md
README-topology.md

• The /usr/share/doc/ansible-freeipa/playbooks/ directory stores the example playbooks:

[root@server]# Is -1 /usr/share/doc/ansible-freeipa/playbooks/install-client.yml
install-cluster.yml
install-replica.yml
install-server.yml
uninstall-client.yml
uninstall-cluster.yml
uninstall-replica.yml
uninstall-replica.yml
uninstall-server.yml

22.5. DEPLOYING AN IDM SERVER WITH AN INTEGRATED CA AS THE ROOT CA USING AN ANSIBLE PLAYBOOK

22.5.1. Setting the parameters for a deployment with an integrated CA as the root CA

Complete this procedure to configure the inventory file for installing an IdM server with an integrated CA as the root CA.

Procedure

- 1. Open the inventory file for editing. Specify the fully-qualified domain names (**FQDN**) of the host you want to use as an IdM server. Ensure that the **FQDN** meets the following criteria:
 - Only alphanumeric characters and hyphens (-) are allowed. For example, underscores are not allowed and can cause DNS failures.
 - The host name must be all lower-case.
- 2. Specify the IdM domain and realm information.
- 3. Specify if you want the IdM server to have an integrated DNS and if you want it to use forwarders from the /etc/resolv.conf file.
- 4. Specify the passwords for **admin** and for the **Directory Manager**. Use the Ansible Vault to store the password, and reference the Vault file from the playbook file. Alternatively and less securely, specify the passwords directly in the inventory file.
- 5. (Optional) Specify a custom **firewalld** zone to be used by the IdM server. If you do not set a custom zone, IdM will add its services to the default **firewalld** zone. The predefined default zone is **public**.



IMPORTANT

The specified **firewalld** zone must exist and be permanent.

Example of an inventory file with the required server information (excluding the passwords)

```
[ipaserver]
server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=yes
ipaserver_auto_forwarders=yes
[...]
```

Example of an inventory file with the required server information (including the passwords)

```
[ipaserver]
server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=yes
ipaserver_auto_forwarders=yes
ipaadmin_password=MySecretPassword123
ipadm_password=MySecretPassword234

[...]
```

Example of an inventory file with a custom firewalld zone

```
[ipaserver]
server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=yes
ipaserver_auto_forwarders=yes
ipaadmin_password=MySecretPassword123
ipadm_password=MySecretPassword234
ipaserver_firewalld_zone=custom zone
```

Example playbook to set up an IdM server using admin and Directory Manager passwords stored in an Ansible Vault file

```
---
- name: Playbook to configure IPA server hosts: ipaserver become: true vars_files:
- playbook_sensitive_data.yml
```

roles:

 role: ipaserver state: present

Example playbook to set up an IdM server using admin and Directory Manager passwords from an inventory file

- name: Playbook to configure IPA server

hosts: ipaserver become: true

roles:

 role: ipaserver state: present

For details on installing the IdM server and the available options, see https://access.redhat.com/documentation/en-us/red_hat_enterprise_linux/8/html-single/installing_identity_management/index#installing-idm.

22.5.2. Deploying an IdM server with an integrated CA as the root CA using an Ansible playbook

Complete this procedure to deploy an IdM server with an integrated certificate authority (CA) as the root CA using an Ansible playbook.

Procedure

Run the ansible-playbook command with the name of the playbook file, for example install-server.yml. Specify the inventory file with the -i option:

\$ ansible-playbook -v -i <path_to_inventory_directory>/hosts <path_to_playbooks_directory>/install-server.yml

Specify the level of verbosity by using the **-v**, **-vv**, or **-vvv** option.

You can view the output of the Ansible playbook script on the command-line interface (CLI). The following output shows that the script has run successfully as O tasks have failed:

PLAY RECAP

server.idm.example.com : ok=18 changed=10 unreachable=0 failed=0 skipped=21 rescued=0 ignored=0

You have installed an IdM server on your host using an Ansible playbook.

22.6. DEPLOYING AN IDM SERVER WITH AN EXTERNAL CA AS THE ROOT CA USING AN ANSIBLE PLAYBOOK

22.6.1. Setting the parameters for a deployment with an external CA as the root CA

Complete this procedure to configure the inventory file for installing an IdM server with an external CA as the root CA.

Procedure

- 1. Open the inventory file for editing. Specify the fully-qualified domain names (**FQDN**) of the host you want to use as an IdM server. Ensure that the **FQDN** meets the following criteria:
 - Only alphanumeric characters and hyphens (-) are allowed. For example, underscores are not allowed and can cause DNS failures.
 - The host name must be all lower-case.
- 2. Specify the IdM domain and realm information.
- 3. Specify if you want the IdM server to have an integrated DNS and if you want it to use forwarders from the /etc/resolv.conf file.
- 4. Specify the passwords for **admin** and for the **Directory Manager**. Use the Ansible Vault to store the password, and reference the Vault file from the playbook file. Alternatively and less securely, specify the passwords directly in the inventory file.
- 5. (Optional) Specify a custom **firewalld** zone to be used by the IdM server. If you do not set a custom zone, IdM will add its services to the default **firewalld** zone. The predefined default zone is **public**.



[ipaserver]

[...]

IMPORTANT

The specified **firewalld** zone must exist and be permanent.

Example of an inventory file with the required server information (excluding the passwords)

server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=yes
ipaserver_auto_forwarders=yes

Example of an inventory file with the required server information (including the passwords)

[ipaserver] server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=yes
ipaserver_auto_forwarders=yes
ipaadmin_password=MySecretPassword123
ipadm_password=MySecretPassword234

[...]

Example of an inventory file with a custom firewalld zone

```
[ipaserver]
server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=yes
ipaserver_auto_forwarders=yes
ipaadmin_password=MySecretPassword123
ipadm_password=MySecretPassword234
ipaserver_firewalld_zone=custom zone

[...]
```

6. Create a playbook for the first step of the installation. Enter instructions for generating the certificate signing request (CSR) and copying it from the controller to the managed node.

```
-name: Playbook to configure IPA server Step 1
hosts: ipaserver
become: true
vars_files:
- playbook_sensitive_data.yml
vars:
    ipaserver_external_ca: yes

roles:
- role: ipaserver
    state: present

post_tasks:
- name: Copy CSR /root/ipa.csr from node to "{{ groups.ipaserver[0] + '-ipa.csr' }}"
fetch:
    src: /root/ipa.csr
    dest: "{{ groups.ipaserver[0] + '-ipa.csr' }}"
flat: yes
```

7. Create another playbook for the final step of the installation.

```
---
- name: Playbook to configure IPA server Step -1
hosts: ipaserver
become: true
vars_files:
- playbook_sensitive_data.yml
vars:
    ipaserver_external_cert_files: "/root/chain.crt"

pre_tasks:
- name: Copy "{{ groups.ipaserver[0] + '-chain.crt' }}" to /root/chain.crt on node
copy:
    src: "{{ groups.ipaserver[0] + '-chain.crt' }}"
dest: "/root/chain.crt"
```

force: yes

roles:

 role: ipaserver state: present

For details on the options available to you when installing an IdM server with an externally signed CA, see https://access.redhat.com/documentation/en-us/red_hat_enterprise_linux/8/html-single/installing_identity_management/index#installing-an-ipa-server-with-external-ca_installing-identity-management.

22.6.2. Deploying an IdM server with an external CA as the root CA using an Ansible playbook

Complete this procedure to deploy an IdM server with an external certificate authority (CA) as the root CA using an Ansible playbook.

Procedure

 Run the ansible-playbook command with the name of the playbook file that contains instructions for the first step of the installation, for example install-server-step1.yml. Specify the inventory file with the -i option:

\$ ansible-playbook -v -i <path_to_inventory_directory>/host.server <path_to_playbooks_directory>/install-server-step1.yml

Specify the level of verbosity by using the **-v**, **-vv** or **-vvv** option.

You can view the output of the Ansible playbook script on the command-line interface (CLI). The following output shows that the script has run successfully as O tasks have failed:

PLAY RECAP

server.idm.example.com : ok=18 changed=10 unreachable=0 **failed=0** skipped=21 rescued=0 ignored=0

- 2. Locate the **ipa.csr** certificate signing request file on the controller and submit it to the external CA.
- 3. Place the IdM CA certificate signed by the external CA in the controller file system so that the playbook in the next step can find it.
- 4. Run the **ansible-playbook** command with the name of the playbook file that contains instructions for the final step of the installation, for example **install-server-step2.yml**. Specify the inventory file with the **-i** option:

\$ ansible-playbook -v -i <path_to_inventory_directory>/host.server <path_to_playbooks_directory>/install-server-step2.yml

You have installed an IdM server with an externally signed CA on your host using an Ansible playbook.

CHAPTER 23. INSTALLING AN IDENTITY MANAGEMENT REPLICA USING AN ANSIBLE PLAYBOOK

23.1. IDM REPLICA INSTALLATION USING AN ANSIBLE PLAYBOOK

The following sections describe how to configure a system as an IdM replica by using Ansible. Configuring a system as an IdM replica enrolls it into an IdM domain and enables the system to use IdM services on IdM servers in the domain.

The deployment is managed by the **ipareplica** Ansible role. The role can use the autodiscovery mode for identifying the IdM servers, domain and other settings. However, if you deploy multiple replicas in a tierlike model, with different groups of replicas being deployed at different times, you must defined specific servers or replicas for each group.



NOTE

Before installing an IdM replica using Ansible, ensure that you understand Ansible and IdM concepts. Ensure that you understand the following terms that are used in this chapter:

- Ansible roles
- Ansible nodes
- Ansible inventory
- Ansible tasks
- Ansible modules
- Ansible plays and playbooks

Overview

The installation consists of the following parts:

- 1. Setting the parameters of the IdM replica deployment
 - Specifying the base, server and client variables for installing the IdM replica
 - Specifying the credentials for installing the IdM replica using an Ansible playbook
- 2. Deploying an IdM replica using an Ansible playbook

Prerequisites

• You have installed the ansible-freeipa package on the Ansible control node.

23.2. SETTING THE PARAMETERS OF THE IDM REPLICA DEPLOYMENT

Before you deploy a target host as an IdM replica, configure the following settings:

• Specify the base, server and client variables for installing the IdM replica.

• Specify the credentials for installing the IdM replica using an Ansible playbook.

23.2.1. Specifying the base, server and client variables for installing the IdM replica

Complete this procedure to configure the inventory file for installing an IdM replica.

Procedure

- Open the inventory file for editing. Specify the fully-qualified domain names (FQDN) of the hosts to become IdM replicas. The FQDNs must be valid DNS names:
 - Only numbers, alphabetic characters, and hyphens (-) are allowed. For example, underscores are not allowed and can cause DNS failures.
 - The host name must be all lower-case.

Example of a simple inventory hosts file with only the replicas' FQDN defined

```
[ipareplicas]
replica1.idm.example.com
replica2.idm.example.com
replica3.idm.example.com
[...]
```

If the IdM server is already deployed and the SRV records are set properly in the IdM DNS zone, the script automatically discovers all the other required values.

2. Optionally, provide additional information in the inventory file based on which of the following scenarios is closest to yours:

Scenario 1

If you want to avoid autodiscovery and have all replicas listed in the **[ipareplicas]** section use a specific IdM server, set the server in the **[ipaservers]** section of the inventory file.

Example inventory hosts file with the FQDN of the IdM server and replicas defined

```
[ipaservers] server.idm.example.com
```

[ipareplicas]
replica1.idm.example.com
replica2.idm.example.com
replica3.idm.example.com
[...]

• Scenario 2

Alternatively, if you want to avoid autodiscovery but want to deploy specific replicas with specific servers, set the servers for specific replicas individually in the **[ipareplicas]** section in the inventory file.

Example inventory file with a specific IdM server defined for a specific replica

[ipaservers]

server.idm.example.com replica1.idm.example.com

[ipareplicas]
replica2.idm.example.com
replica3.idm.example.com ipareplica_servers=replica1.idm.example.com

In the example above, **replica3.idm.example.com** uses the already deployed **replica1.idm.example.com** as its replication source.

Scenario 3

If you are deploying several replicas in one batch and time is a concern to you, multitier replica deployment can be useful for you. Define specific groups of replicas in the inventory file, for example [ipareplicas_tier1] and [ipareplicas_tier2], and design separate plays for each group in the install-replica.yml playbook.

Example inventory file with replica tiers defined

[ipaservers] server.idm.example.com

[ipareplicas_tier1]

replica1.idm.example.com

[ipareplicas_tier2]

replica2.idm.example.com \

ipareplica_servers=replica1.idm.example.com,server.idm.example.com

The first entry in **ipareplica_servers** will be used. The second entry will be used as a fallback option. When using multiple tiers for deploying IdM replicas, you must have separate tasks in the playbook to first deploy replicas from tier1 and then replicas from tier2:

Example of a playbook file with different plays for different replica groups

- name: Playbook to configure IPA replicas (tier1)

hosts: ipareplicas_tier1

become: true

roles:

 role: ipareplica state: present

- name: Playbook to configure IPA replicas (tier2)

hosts: ipareplicas_tier2

become: true

roles:

 role: ipareplica state: present

Scenario 4

If you want the replica to use a specified **firewalld** zone instead of the default one, you can specify it in the inventory file. This can be useful, for example, when you want to use an internal **firewalld** zone for your IdM installation instead of a public zone that is set as

default.

If you do not set a custom zone, IdM will add its services to the default **firewalld** zone. The predefined default zone is **public**.



IMPORTANT

The specified **firewalld** zone must exist and be permanent.

Example of a simple inventory hosts file with a custom firewalld zone

[ipaservers] server.idm.example.com

[ipareplicas] replica1.idm.example.com replica2.idm.example.com replica3.idm.example.com [...]

[ipareplicas:vars] ipareplica_firewalld_zone=custom zone

23.2.2. Specifying the credentials for installing the IdM replica using an Ansible playbook

Complete this procedure to configure the authorization for installing the IdM replica.

Procedure

- 1. Specify the password of a user authorized to deploy replicas for example the IdM admin.
 - Red Hat recommends using the Ansible Vault to store the password, and referencing the Vault file from the playbook file, for example **install-replica.yml**:

Example playbook file using principal from inventory file and password from an Ansible Vault file

- name: Playbook to configure IPA replicas

hosts: ipareplicas become: true vars_files:

- playbook_sensitive_data.yml

roles:

 role: ipareplica state: present

For details how to use Ansible Vault, see the official Ansible Vault documentation.

Less securely, provide the credentials of admin directly in the inventory file. Use the
ipaadmin_password option in the [ipareplicas:vars] section of the inventory file. The
inventory file and the install-replica.yml playbook file can then look as follows:

Example inventory hosts.replica file

[...]
[ipareplicas:vars]
ipaadmin_password=Secret123

Example playbook using principal and password from inventory file

- name: Playbook to configure IPA replicas

hosts: ipareplicas become: true

roles:

 role: ipareplica state: present

Alternatively but also less securely, provide the credentials of another user authorized to
deploy a replica directly in the inventory file. To specify a different authorized user, use the
ipaadmin_principal option for the user name, and the ipaadmin_password option for the
password. The inventory file and the install-replica.yml playbook file can then look as
follows:

Example inventory hosts.replica file

[...]
[ipareplicas:vars]
ipaadmin_principal=my_admin
ipaadmin_password=my_admin_secret123

Example playbook using principal and password from inventory file

- name: Playbook to configure IPA replicas

hosts: ipareplicas become: true

roles:

 role: ipareplica state: present

Additional resources

• For details on the options accepted by the **ipareplica** Ansible role, see the /usr/share/ansible/roles/ipareplica/README.md Markdown file.

23.3. DEPLOYING AN IDM REPLICA USING AN ANSIBLE PLAYBOOK

Complete this procedure to use an Ansible playbook to deploy an IdM replica.

Procedure

 To install an IdM replica using an Ansible playbook, use the ansible-playbook command with the name of the playbook file, for example install-replica.yml. Specify the inventory file with the -i option:

\$ ansible-playbook -v -i <path_to_inventory_directory>/hosts.replica <path_to_playbooks_directory>/install-replica.yml

Specify the level of verbosity by using the **-v**, **-vv** or **-vvv** option.

Ansible informs you about the execution of the Ansible playbook script. The following output shows that the script has run successfully as 0 tasks have failed:

PLAY RECAP

replica.idm.example.com : ok=18 changed=10 unreachable=0 **failed=0** skipped=21 rescued=0 ignored=0

You have now installed an IdM replica.

CHAPTER 24. INSTALLING AN IDENTITY MANAGEMENT CLIENT USING AN ANSIBLE PLAYBOOK

24.1. IDM CLIENT INSTALLATION USING AN ANSIBLE PLAYBOOK

The following sections describe how to configure a system as an Identity Management (IdM) client by using Ansible. Configuring a system as an IdM client enrolls it into an IdM domain and enables the system to use IdM services on IdM servers in the domain.

The deployment is managed by the **ipaclient** Ansible role. By default, the role uses the autodiscovery mode for identifying the IdM servers, domain and other settings. The role can be modified to have the Ansible playbook use the settings specified, for example in the inventory file.



NOTE

Before installing an IdM client using Ansible, ensure that you understand Ansible and IdM concepts. Ensure that you understand the following terms that are used in this chapter:

- Ansible roles
- Ansible nodes
- Ansible inventory
- Ansible tasks
- Ansible modules
- Ansible plays and playbooks

Overview

The installation consists of the following parts:

- 1. Setting the parameters of the IdM client deployment to correspond to your deployment scenario:
 - Setting the parameters of the inventory file for the autodiscovery client installation mode;
 - Setting the parameters of the inventory file for when autodiscovery is not possible during client installation;
- 2. Checking the parameters in install-client.yml;
- 3. Deploying an IdM client using an Ansible playbook;
- 4. Testing an Identity Management client after installation .

The chapter also includes a section describing how to uninstall an IdM client .

Prerequisites

• You have installed the ansible-freeipa package on the Ansible control node.

24.2. SETTING THE PARAMETERS OF THE IDM CLIENT DEPLOYMENT

Before you deploy a target host as an IdM client, configure the deployment instructions on the control node. Additionally, configure the target host parameters depending on which of the following options you are planning:

- Using the autodiscovery client installation mode
- Specifying the **FQDN** of the IdM server and the domain or realm information .

24.2.1. Setting the parameters of the inventory file for the autodiscovery client installation mode

To install an Identity Management client using an Ansible playbook, provide the following information in an inventory file, for example **inventory/hosts**:

- the information about the host
- the authorization for the task

The inventory file can be in one of many formats, depending on the inventory plugins you have. The **INI-like** format is one of Ansible's defaults and is used in the examples below.



NOTE

To use smart cards with the graphical user interface in RHEL, ensure that you include the **ipaclient_mkhomedir** variable in your Ansible playbook.

Procedure

- 1. Specify the fully-qualified hostname (**FQDN**) of the host to become an IdM client. The fully qualified domain name must be a valid DNS name:
 - Only numbers, alphabetic characters, and hyphens (-) are allowed. For example, underscores are not allowed and can cause DNS failures.
 - The host name must be all lower-case. No capital letters are allowed.

 If the SRV records are set properly in the IdM DNS zone, the script automatically discovers all the other required values.

Example of a simple inventory hosts file with only the client FQDN defined

[ipaclients] client.idm.example.com [...]

- 2. Specify the credentials for enrolling the client. The following authentication methods are available:
 - The password of a user authorized to enroll clients This is the default option.
 - Red Hat recommends using the Ansible Vault to store the password, and referencing the Vault file from the playbook file, for example **install-client.yml**, directly:

Example playbook file using principal from inventory file and password from an Ansible Vault file

- name: Playbook to configure IPA clients with username/password

hosts: ipaclients become: true vars files:

- playbook_sensitive_data.yml

roles

- role: ipaclient state: present

• Less securely, provide the credentials of admin using the ipaadmin_password option in the [ipaclients:vars] section of the inventory/hosts file. Alternatively, to specify a different authorized user, use the ipaadmin_principal option for the user name, and the ipaadmin_password option for the password. The inventory/hosts inventory file and the install-client.yml playbook file can then look as follows:

Example inventory hosts file

[...]
[ipaclients:vars]
ipaadmin_principal=my_admin
ipaadmin_password=Secret123

Example Playbook using principal and password from inventory file

- name: Playbook to unconfigure IPA clients

hosts: ipaclients become: true

roles:

role: ipaclient state: true

- The **client keytab** from the previous enrollment if it is still available:
 - This option is available if the system was previously enrolled as an Identity Management client. To use this authentication method, uncomment the #ipaclient_keytab option, specifying the path to the file storing the keytab, for example in the [ipaclient:vars] section of inventory/hosts.
- A random, one-time password (OTP) to be generated during the enrollment. To use this
 authentication method, use the ipaclient_use_otp=yes option in your inventory file. For
 example, you can uncomment the ipaclient_use_otp=yes option in the [ipaclients:vars]
 section of the inventory/hosts file. Note that with OTP you must also specify one of the
 following options:
 - The password of a user authorized to enroll clients for example by providing a value for ipadmin_password in the [ipaclients:vars] section of the inventory/hosts file.
 - The admin keytab, for example by providing a value for ipaadmin_keytab in the [ipaclients:vars] section of inventory/hosts.

Additional resources

 For details on the options accepted by the ipaclient Ansible role, see the /usr/share/ansible/roles/ipaclient/README.md README file.

24.2.2. Setting the parameters of the inventory file when autodiscovery is not possible during client installation

To install an Identity Management client using an Ansible playbook, provide the following information in an inventory file, for example **inventory/hosts**:

- the information about the host, the IdM server and the IdM domain or the IdM realm
- the authorization for the task

The inventory file can be in one of many formats, depending on the inventory plugins you have. The **INI-like** format is one of Ansible's defaults and is used in the examples below.



NOTE

To use smart cards with the graphical user interface in RHEL, ensure that you include the **ipaclient_mkhomedir** variable in your Ansible playbook.

Procedure

- 1. Specify the fully-qualified hostname (**FQDN**) of the host to become an IdM client. The fully qualified domain name must be a valid DNS name:
 - Only numbers, alphabetic characters, and hyphens (-) are allowed. For example, underscores are not allowed and can cause DNS failures.
 - The host name must be all lower-case. No capital letters are allowed.
- 2. Specify other options in the relevant sections of the **inventory/hosts** file:
 - the **FQDN** of the servers in the **[ipaservers]** section to indicate which IdM server the client will be enrolled with
 - one of the two following options:
 - the **ipaclient_domain** option in the **[ipaclients:vars]** section to indicate the DNS domain name of the IdM server the client will be enrolled with
 - the **ipaclient_realm** option in the **[ipaclients:vars]** section to indicate the name of the Kerberos realm controlled by the IdM server

Example of an inventory hosts file with the client FQDN, the server FQDN and the domain defined

[ipaclients]
client.idm.example.com

[ipaservers]
server.idm.example.com

[ipaclients:vars]
ipaclient_domain=idm.example.com
[...]

- 3. Specify the credentials for enrolling the client. The following authentication methods are available:
 - The password of a user authorized to enroll clients This is the default option.
 - Red Hat recommends using the Ansible Vault to store the password, and referencing the Vault file from the playbook file, for example **install-client.yml**, directly:

Example playbook file using principal from inventory file and password from an Ansible Vault file

- name: Playbook to configure IPA clients with username/password

hosts: ipaclients become: true vars_files:

- playbook_sensitive_data.yml

roles:

 role: ipaclient state: present

• Less securely, provide the credentials of admin using the ipaadmin_password option in the [ipaclients:vars] section of the inventory/hosts file. Alternatively, to specify a different authorized user, use the ipaadmin_principal option for the user name, and the ipaadmin_password option for the password. The install-client.yml playbook file can then look as follows:

Example inventory hosts file

[...]
[ipaclients:vars]
ipaadmin_principal=my_admin
ipaadmin_password=Secret123

Example Playbook using principal and password from inventory file

- name: Playbook to unconfigure IPA clients

hosts: ipaclients become: true

roles:

 role: ipaclient state: true

- The **client keytab** from the previous enrollment if it is still available:
 - This option is available if the system was previously enrolled as an Identity Management client. To use this authentication method, uncomment the **ipaclient_keytab** option, specifying the path to the file storing the keytab, for example in the **[ipaclient:vars]** section of **inventory/hosts**.
- A random, one-time password (OTP) to be generated during the enrollment. To use this
 authentication method, use the ipaclient_use_otp=yes option in your inventory file. For
 example, you can uncomment the #ipaclient_use_otp=yes option in the [ipaclients:vars]

section of the **inventory/hosts** file. Note that with OTP you must also specify one of the following options:

- The password of a user authorized to enroll clients for example by providing a value for ipadmin_password in the [ipaclients:vars] section of the inventory/hosts file.
- The admin keytab, for example by providing a value for ipaadmin_keytab in the [ipaclients:vars] section of inventory/hosts.

Additional resources

• For details on the options accepted by the **ipaclient** Ansible role, see the /usr/share/ansible/roles/ipaclient/README.md README file.

24.2.3. Checking the parameters in the install-client.yml file

The install-client.yml playbook file contains instructions for the IdM client deployment.

• Open the file and check if the instructions in the playbook correspond to what you are planning for your deployment. The contents typically look like this:

- name: Playbook to configure IPA clients with username/password

hosts: ipaclients become: true

roles:

 role: ipaclient state: present

This is what the individual entries mean:

- The hosts entry specifies the section of the **inventory/hosts** file where the ansible script searches the **FQDNs** of the hosts on which the **ipa-client-install** script shall be run.
- The **become: true** entry specifies that root's credentials will be invoked during the execution of the **ipa-client-install** script.
- The **role: ipaclient** entry specifies the role that will be installed on the host: in this case, it is the ipa client role.
- The **state: present** entry specifies that the client should be installed rather than uninstalled (**absent**).

24.2.4. Authorization options for IdM client enrollment using an Ansible playbook

This referential section presents individual authorization options for IdM client enrollment with examples of inventory and playbook files.

Table 24.1. Authorization options for IdM client enrollment using Ansible

Authorizat ion option	Note	Example inventory file	Example install-client.yml playbook file
Password of a user authorized to enroll a client: Option 1	Password stored in Ansible vault	[ipaclients:vars] []	- name: Playbook to configure IPA clients with username/password hosts: ipaclients become: true vars_files: - playbook_sensitive_data.yml roles: - role: ipaclient state: present
Password of a user authorized to enroll a client: Option 2	Password stored in inventory file	[ipaclients:vars] ipaadmin_password=Secret123	- name: Playbook to configure IPA clients hosts: ipaclients become: true roles: - role: ipaclient state: true
A random, one-time password (OTP): Option 1	OTP + administrat or password	[ipaclients:vars] ipaadmin_password=Secret123 ipaclient_use_otp=yes	- name: Playbook to configure IPA clients hosts: ipaclients become: true roles: - role: ipaclient state: true
A random, one-time password (OTP): Option 2	OTP + an admin keytab	[ipaclients:vars] ipaadmin_keytab=/tmp/admin.ke ytab ipaclient_use_otp=yes	- name: Playbook to configure IPA clients hosts: ipaclients become: true roles: - role: ipaclient state: true

Authorizat ion option	Note	Example inventory file	Example install-client.yml playbook file
The client keytab from the previous enrollment		[ipaclients:vars] ipaclient_keytab=/tmp/krb5.keyta b	- name: Playbook to configure IPA clients hosts: ipaclients become: true roles: - role: ipaclient state: true

24.3. DEPLOYING AN IDM CLIENT USING AN ANSIBLE PLAYBOOK

Complete this procedure to use an Ansible playbook to deploy an IdM client in your IdM environment.

Procedure

 To install an IdM client using an Ansible playbook, use the ansible-playbook command with the name of the playbook file, for example install-client.yml. Specify the inventory file with the -i option:

\$ ansible-playbook -v -i inventory/hosts install-client.yml

Specify the level of verbosity by using the **-v**, **-vv** or **-vvv** option.

Ansible informs you about the execution of the Ansible playbook script. The following output shows that the script has run successfully as no tasks have failed:

PLAY RECAP

client1.idm.example.com : ok=18 changed=10 unreachable=0 failed=0 skipped=21 rescued=0 ignored=0



NOTE

Ansible uses different colors to provide different types of information about the running process. You can modify the default colors in the **[colors]** section of the **/etc/ansible/ansible.cfg** file:

[colors]
[...]
#error = red
#debug = dark gray
#deprecate = purple
#skip = cyan
#unreachable = red
#ok = green
#changed = yellow
[...]

You have now installed an IdM client on your host using an Ansible playbook.

24.4. TESTING AN IDENTITY MANAGEMENT CLIENT AFTER ANSIBLE INSTALLATION

The command-line interface (CLI) informs you that the **ansible-playbook** command was successful, but you can also do your own test.

To test that the Identity Management client can obtain information about users defined on the server, check that you are able to resolve a user defined on the server. For example, to check the default **admin** user.

[user@client1 ~]\$ **id admin** uid=1254400000(admin) gid=1254400000(admins) groups=1254400000(admins)

To test that authentication works correctly, **su** - as another already existing IdM user:

[user@client1 ~]\$ **su - idm_user**Last login: Thu Oct 18 18:39:11 CEST 2018 from 192.168.122.1 on pts/0
[idm_user@client1 ~]\$

24.5. UNINSTALLING AN IDM CLIENT USING AN ANSIBLE PLAYBOOK

Complete this procedure to use an Ansible playbook to uninstall your host as an IdM client.

Prerequisites

• IdM administrator credentials.

Procedure

• To uninstall the IdM client, use the **ansible-playbook** command with the name of the playbook file, for example **uninstall-client.yml**. Specify the inventory file with the **-i** option and, optionally, specify the level of verbosity by using the **-v**, **-vv** or **-vvv** options:

\$ ansible-playbook -v -i inventory/hosts uninstall-client.yml



IMPORTANT

The uninstallation of the client only removes the basic IdM configuration from the host but leaves the configuration files on the host in case you decide to re-install the client. In addition, the uninstallation has the following limitations:

- It does not remove the client host entry from the IdM LDAP server. The uninstallation only unenrolls the host.
- It does not remove any services residing on the client from IdM.
- It does not remove the DNS entries for the client from the IdM server.
- It does not remove the old principals for keytabs other than /etc/krb5.keytab.

Note that the uninstallation does remove all certificates that were issued for the host by the IdM CA.

Additional resources

• For more information on how to remove the IdM client configuration from both the host and the IdM environment completely, see the manual procedure for Uninstalling an IdM client.

PART II. INTEGRATING IDM AND AD

CHAPTER 25. INSTALLING TRUST BETWEEN IDM AND AD

This chapter aims to help you create a trust between the Identity Management IdM server and Active Directory (AD), where both servers are located in the same forest.

Prerequisites

- First, read the Planning a cross-forest trust between Identity Management and Active Directory document.
- AD is installed with a domain controller on it.
- The IdM server is installed and running.
 - For details, see Installing Identity Management.
- Both the AD server and the IdM server must have their clocks in sync because Kerberos requires max 5 mins delay in communication.
- Unique NetBIOS names for each of the servers placed in the trust because the NetBIOS names are critical for identifying the Active Directory domain.
 - The NetBIOS name of an Active Directory or IdM domain is usually the first part of the
 corresponding DNS domain. If the DNS domain is ad.example.com, the NetBIOS name is
 typically AD. However, it is not required. Important is that the NetBIOS name is just one
 word without periods. The maximum length of a NetBIOS name is 15 characters.
- The IdM system must have the IPv6 protocol enabled in the kernel.
 - If IPv6 is disabled, then the CLDAP plug-in used by the IdM services fails to initialize.

25.1. SUPPORTED VERSIONS OF WINDOWS SERVER

In RHEL 8.4, Identity Management (IdM) does not support establishing trust to Active Directory with Active Directory domain controllers running Windows Server 2008 R2 or earlier versions. RHEL IdM now requires SMB encryption when establishing the trust relationship, which is only supported in Windows Server 2012 or later.

You can establish a trust relationship with Active Directory (AD) forests that use the following forest and domain functional levels:

- Forest functional level range: Windows Server 2012 Windows Server 2016
- Domain functional level range: Windows Server 2012 Windows Server 2016

Identity Management (IdM) supports establishing a trust with Active Directory domain controllers running the following operating systems:

- Windows Server 2012
- Windows Server 2012 R2
- Windows Server 2016
- Windows Server 2019

25.2. HOW THE TRUST WORKS

The trust between Identity Management IdM and Active Directory (AD) is established on the Cross-realm Kerberos trust. This solution uses the Kerberos capability to establish trusts between different identity sources. Therefore, all AD users can:

- Log in to access Linux systems and resources.
- Use single sign-on (SSO).

All IdM objects are managed in IdM in the trust.

All AD objects are managed in AD in the trust.

In complex environments, a single IdM forest can be connected to multiple AD forests. This setup enables better separation of duties for different functions in the organization. AD administrators can focus on users and policies related to users while Linux administrators have full control over the Linux infrastructure. In such a case, the Linux realm controlled by IdM is analogous to an AD resource domain or realm but with Linux systems in it.

From the perspective of AD, Identity Management represents a separate AD forest with a single AD domain. When cross-forest trust between an AD forest root domain and an IdM domain is established, users from the AD forest domains can interact with Linux machines and services from the IdM domain.



NOTE

In trust environments, IdM enables you to use ID views to configure POSIX attributes for AD users on the IdM server.

25.3. AD ADMINISTRATION RIGHTS

When you want to build a trust between AD (Active Directory) and IdM (Identity Management), you will need to use an AD administrator account with appropriate AD privileges.

Such an AD administrator must be a member of one of the following groups:

- Enterprise Admin group in the AD forest
- Domain Admins group in the forest root domain for your AD forest

Related information

- For details about Enterprise Admins, see Enterprise Admins.
- For details about Domain Admins, see Domain Admins.
- For details about AD trust, see How Domain and Forest Trusts Work.

25.4. ENSURING SUPPORT FOR COMMON ENCRYPTION TYPES IN AD AND RHEL

By default, Identity Management establishes a cross-realm trust with support for RC4, AES-128, and AES-256 Kerberos encryption types.

RC4 encryption has been deprecated and disabled by default in RHEL 8, as it is considered less secure

than the newer AES-128 and AES-256 encryption types. In contrast, Active Directory (AD) user credentials and trusts between AD domains support RC4 encryption and they might not support AES encryption types.

Without any common encryption types, communication between IdM and AD child domains might not work, or some AD accounts might not be able to authenticate. To remedy this situation, modify one of the following configurations:

- Enable AES encryption support in Active Directory (recommended option) To ensure trusts between AD domains in an AD forest support strong AES encryption types, see the following Microsoft article: AD DS: Security: Kerberos "Unsupported etype" error when accessing a resource in a trusted domain
- Enable RC4 support in RHEL: On every IdM trust controller, trust agent, and client where authentication against AD Domain Controllers takes place:
 - 1. Use the **update-crypto-policies** command to enable the **AD-SUPPORT** cryptographic subpolicy in addition to the **DEFAULT** cryptographic policy.

[root@host ~]# update-crypto-policies --set DEFAULT:AD-SUPPORT Setting system policy to DEFAULT:AD-SUPPORT Note: System-wide crypto policies are applied on application start-up. It is recommended to restart the system for the change of policies to fully take place.

2. Restart the host.



IMPORTANT

The **AD-SUPPORT** cryptographic subpolicy is only available on RHEL 8.3 and newer.

- To enable support for RC4 in RHEL 8.2, create and enable a custom cryptographic module policy with cipher = RC4-128+. For more details, see Customizing system-wide cryptographic policies with policy modifiers.
- To enable support for RC4 in RHEL 8.0 and RHEL 8.1, add +rc4 to the permitted_enctypes option in the /etc/crypto-policies/back-ends/krb5.config file:

[libdefaults]

permitted_enctypes = aes256-cts-hmac-sha1-96 aes256-cts-hmac-sha384-192 camellia256-cts-cmac aes128-cts-hmac-sha1-96 aes128-cts-hmac-sha256-128 camellia128-cts-cmac +rc4

Additional resources

- For more information on working with RHEL cryptographic policies, see Using system-wide cryptographic policies in the Security Hardening guide.
- For more information on IdM trust agents and trust controllers, see Trust controllers and trust agents in the Planning Identity Management guide.

25.5. PORTS REQUIRED FOR COMMUNICATION BETWEEN IDM AND AD

To enable communication between your Active Directory (AD) and Identity Management (IdM) environments, open the following ports on the firewalls of your AD Domain Controllers and IdM servers.

Table 25.1. Ports required for an AD trust

Service	Port	Protocol
Endpoint resolution portmapper	135	TCP
NetBIOS-DGM	138	TCP and UDP
NetBIOS-SSN	139	TCP and UDP
Microsoft-DS	445	TCP and UDP
Dynamic RPC	49152-65535	TCP
AD Global Catalog	3268	TCP
LDAP	389	TCP and UDP



NOTE

The TCP port 389 is not required to be open on IdM servers for trust, but it is necessary for clients communicating with the IdM server.

To open ports, you can use the following methods:

- Firewalld service you can enable the particular ports or enable the following services which includes the ports:
 - FreeIPA trust setup
 - FreeIPA with LDAP
 - Kerberos
 - DNS

For details, see Controlling ports using CLI.



NOTE

The **freeipa-trust** Firewalld service currently includes an RPC port range of **1024-1300**, but this range has been updated to **49152-65535** in Windows Server 2008 and later. The **freeipa-trust** Firewalld service will be updated to reflect this new range, and this issue is tracked in Bug 1850418 – update freeipa-trust.xml definition to include correct dynamic RPC range.

Until that bug has been resolved, manually open the TCP port range **49152-65535** in addition to enabling the **freeipa-trust** Firewalld service.

RED HAT ENTERPRISE LINUX server.idm.ex... ~ Networking > Firewall Firewall Allowed Services Cockpit **=** 9090 # DHCPv6 Client 546 * DNS 53 FreeIPA trust setup 135, 138-139, 389, 445, 1024-1300, 3268 138-139, 389, 445 * FreeIPA with LDAP 80, 443, 88, 464, 389 88, 464, 123 FreeIPA with LDAPS 80, 443, 88, 464, 636 88, 464, 123 • Kerberos *

• The RHEL web console, which is a UI with firewall settings based on the **firewalld** service.

For details about firewall configuration through the web console, see Enabling services on the firewall using the web console.



NOTE

The **FreeIPA Trust Setup** service currently includes an RPC port range of **1024-1300**, but this range has been updated to **49152-65535** in Windows Server 2008 and later. The **FreeIPA Trust Setup** firewall service definition will be updated, and this issue is tracked in Bug 1850418 – update freeipa-trust.xml definition to include correct dynamic RPC range.

Until that bug has been resolved, manually open the TCP port range **49152-65535** in addition to enabling the **FreeIPA Trust Setup** service in the RHEL web console.

Table 25.2. Ports required by IdM servers in a trust

Service	Port	Protocol
Kerberos	88, 464	TCP and UDP
LDAP	389	TCP
DNS	53	TCP and UDP

Table 25.3. Ports required by IdM clients in an AD trust

Service	Port	Protocol
Kerberos	88	UDP and TCP



NOTE

The **libkrb5** library uses UDP and falls back to the TCP protocol if the data sent from the Key Distribution Centre (KDC) is too large. Active Directory attaches a Privilege Attribute Certificate (PAC) to the Kerberos ticket, which increases the size and requires to use the TCP protocol. To avoid the fall-back and resending the request, by default, SSSD in Red Hat Enterprise Linux 7.4 and later uses TCP for user authentication. If you want to configure the size before libkrb5 uses TCP, set the **udp_preference_limit** in the /etc/krb.5.conf file. For details, see the krb5.conf(5) man page.

Additional resources

For more information on the Dynamic RPC port range in Windows Server 2008 and later, see
The default dynamic port range for TCP/IP has changed since Windows Vista and in Windows
Server 2008.

25.6. CONFIGURING DNS AND REALM SETTINGS FOR A TRUST

Before you connect Identity Management (IdM) and Active Directory (AD) in a trust, you need to ensure that servers see each other and resolve domain names correctly. This scenario describes configuring DNS to allow using domain names between:

- One primary IdM server using integrated DNS server and Certification Authority.
- One AD Domain Controller.

DNS settings require:

- Configuring DNS zones in the IdM server
- Configuring conditional DNS forwarding in AD
- Verifying correctness of the DNS configuration

25.6.1. Unique primary DNS domains

In Windows, every domain is a Kerberos realm and a DNS domain at the same time. Every domain managed by the domain controller needs to have its own dedicated DNS zone. The same applies when Identity Management (IdM) is trusted by Active Directory (AD) as a forest. AD expects IdM to have its own DNS domain. For the trust setup to work, the DNS domain needs to be dedicated to the Linux environment.

Each system must have its own unique primary DNS domain configured. For example:

- ad.example.com for AD and idm.example.com for IdM
- example.com for AD and idm.example.com for IdM
- ad.example.com for AD and example.com for IdM

The most convenient management solution is an environment where each DNS domain is managed by integrated DNS servers, but it is possible to use any other standard-compliant DNS server as well.

Kerberos realm names as upper-case versions of primary DNS domain names

Kerberos realm names must be the same as the primary DNS domain names, with all letters uppercase. For example, if the domain names are **ad.example.com** for AD and **idm.example.com**

for IdM, the Kerberos realm names are required to be **AD.EXAMPLE.COM** and **IDM.EXAMPLE.COM**.

DNS records resolvable from all DNS domains in the trust

All machines must be able to resolve DNS records from all DNS domains involved in the trust relationship.

IdM and AD DNS Domains

Systems joined to IdM can be distributed over multiple DNS domains. Red Hat recommends that you deploy IdM clients in a DNS zone different to the ones owned by Active Directory. The primary IdM DNS domain must have proper SRV records to support AD trusts.



NOTE

In some environments with trusts between IdM and Active Directory, you can install an IdM client on a host that is part of the Active Directory DNS domain. The host can then benefit from the Linux-focused features of IdM. This is not a recommended configuration and has some limitations. See Configuring IdM clients in an Active Directory DNS domain for more details.

You can acquire a list of the required SRV records specific to your system setup by running the following command:

\$ ipa dns-update-system-records --dry-run

The generated list can look for example like this:

IPA DNS records:

- _kerberos-master._tcp.idm.example.com. 86400 IN SRV 0 100 88 server.idm.example.com.
- _kerberos-master._udp.idm.example.com. 86400 IN SRV 0 100 88 server.idm.example.com.
- _kerberos._tcp.idm.example.com. 86400 IN SRV 0 100 88 server.idm.example.com.
- _kerberos._tcp.idm.example.com. 86400 IN SRV 0 100 88 server.idm.example.com.
- kerberos.idm.example.com. 86400 IN TXT "IDM.EXAMPLE.COM"
- kpasswd. tcp.idm.example.com. 86400 IN SRV 0 100 464 server.idm.example.com.
- _kpasswd._udp.idm.example.com. 86400 IN SRV 0 100 464 server.idm.example.com.
- Idap. tcp.idm.example.com. 86400 IN SRV 0 100 389 server.idm.example.com.
- _ipa-ca.idm.example.com. 86400 IN A 192.168.122.2

For other DNS domains that are part of the same IdM realm, it is not required for the SRV records to be configured when the trust to AD is configured. The reason is that AD domain controllers do not use SRV records to discover KDCs but rather base the KDC discovery on name suffix routing information for the trust.

25.6.2. Configuring DNS zones in the IdM Web UI

This section describes how to add a new DNS forward zone to the Identity Management (IdM) server.

DNS forward zones enables you to forward DNS queries for a specific zone to a different DNS server.

For example, on your IdM server, you want to forward queries for the Active Directory (AD) domain.


Prerequisites

Access to the IdM Web UI with a user account which have administrator rights.


• Correctly configured DNS server.

Procedure

- 1. Log in to the IdM Web UI with administrator privileges. For details, see Accessing the IdM Web UI in a web browser.
- 2. Click on the **Network Services** tab.
- 3. Click on the **DNS** tab.
- 4. In the drop down menu, click on the **DNS Forward Zones** item.



- 5. Click on the **Add** button.
- 6. In the Add DNS forward zone dialog box, add a zone name.
- 7. In the **Zone forwarders** item, click on the **Add** button.
- 8. In the **Zone forwarders** field, add the IP address of the server for which you want to create the new forward zone.
- 9. Click on the **Add** button.




The forwarded zone has been added to the DNS settings and you can verify it in the DNS Forward Zones settings. The Web UI informs you about success with the following pop-up message: **DNS Forward Zone successfully added.**

You can perform the same procedure in the command line with the following command:

ipa dnsforwardzone-add \$AD_DOMAIN --forwarder=\$AD_IP_ADDR --forward-policy=first

NOTE

The Web UI can display a warning about DNSSEC validation failure after adding a new forward zone to the configuration.



DNSSEC (Domain Name System Security Extensions) secures DNS data with a digital signature to protect DNS from attacks. The DNSSEC service is enabled by default in the IdM server. The warning appeared because the remote DNS server didn't also use the DNSSEC. Now, you can:

- Enable DNSSEC on the remote DNS server.
- Disable the DNSSEC validation in the /etc/named.conf file saved in the IdM server:

dnssec-validation no;

After saving the configuration change, do not forget to restart the ipactl service:

ipactl restart

The warning will not appear again.

To verify that the dns zone has been created successfully, use the **nslookup** command with the name of the remote DNS server:

\$ nslookup ad.example.com Server: 192.168.122.2 Address: 192.168.122.2#53

No-authoritative answer: ad.example.com Name:

Address: 192.168.122.3

If the domain forwarding is configured correctly, **nslookup** will show you an IP address of the remote DNS server.

25.6.3. Configuring DNS forwarding in AD

This section describes how to set up a DNS forwarding in Active Directory (AD) for the Identity Management (IdM) server.

Prerequisites

- Windows Server with AD installed.
- DNS port open on both servers.

Procedure

- 1. Log in to the Windows Server.
- 2. Open Server Manager.
- 3. Open DNS Manager.
- 4. In Conditional Forwarders, add a new conditional forwarder with:
 - The IdM server IP address
 - A fully qualified domain name, for example, **server.idm.example.com**
- 5. Save the settings.

25.6.4. Verifying the DNS configuration

Before configuring trust, verify that the Identity Management (IdM) and Active Directory (AD) servers can resolve themselves and each other.

Prerequisites

You need to be logged in with sudo permissions.

Procedure

1. Run a DNS guery for the Kerberos over UDP and LDAP over TCP service records.

```
[admin@server ~]# dig +short -t SRV _kerberos._udp.idm.example.com. 0 100 88 server.idm.example.com.
```

[admin@server ~]# dig +short -t SRV _ldap._tcp.idm.example.com. 0 100 389 server.idm.example.com.

The commands are expected to list all IdM servers.

2. Run a DNS query for the TXT record with the IdM Kerberos realm name. The obtained value is expected to match the Kerberos realm you specified when installing IdM.

```
[admin@server ~]# dig +short -t TXT _kerberos.idm.example.com. 
"IDM.EXAMPLE.COM"
```

If the previous steps did not return all the expected records, update the DNS configuration with the missing records:

• If your IdM environment uses an integrated DNS server, enter the **ipa dns-update-system-records** command without any options to update your system records:

[admin@server ~]\$ ipa dns-update-system-records

- If your IdM environment does not use an integrated DNS server:
 - 1. On the IdM server, export the IdM DNS records into a file:

[admin@server ~]\$ ipa dns-update-system-records --dry-run --out dns_records_file.nsupdate

The command creates a file named **dns_records_file.nsupdate** with the relevant IdM DNS records.

- Submit a DNS update request to your DNS server using the nsupdate utility and the dns_records_file.nsupdate file. For more information, see Updating External DNS Records Using nsupdate in RHEL 7 documentation. Alternatively, refer to your DNS server documentation for adding DNS records.
- 3. Verify that IdM is able to resolve service records for AD with a command that runs a DNS query for Kerberos and LDAP over TCP service records:

[admin@server ~]# dig +short -t SRV _kerberos._tcp.dc._msdcs.ad.example.com. 0 100 88 addc1.ad.example.com.

[admin@server ~]# dig +short -t SRV _ldap._tcp.dc._msdcs.ad.example.com. 0 100 389 addc1.ad.example.com.

25.7. CONFIGURING IDM CLIENTS IN AN ACTIVE DIRECTORY DNS DOMAIN

If you have client systems in a DNS domain controlled by Active Directory and you require those clients to be able to join the IdM Server to benefit from its RHEL features, you can configure users to access a client using a host name from the Active Directory DNS domain.



IMPORTANT

This is not a recommended configuration and has some limitations. Red Hat recommends to always deploy IdM clients in a DNS zone different from the ones owned by Active Directory and access IdM clients through their IdM host names.

Your IdM client configuration depends on whether you require single sign-on with Kerberos.

25.7.1. Configuring an IdM client without Kerberos single sign-on

Password authentication is the only authentication method that is available for users to access resources on IdM clients if the IdM clients are in an Active Directory DNS domain. This procedure describes how to configure your client without Kerberos single sign-on.

Procedure

 Install the IdM client with the --domain=IPA_DNS_Domain option to ensure the System Security Services Daemon(SSSD) can communicate with the IdM servers:

[root@idm-client.ad.example.com ~]# ipa-client-install --domain=idm.example.com

This option disables the SRV record auto-detection for the Active Directory DNS domain.

2. Open the /etc/krb5.conf configuration file and locate the existing mapping for the Active Directory domain in the [domain_realm] section.

```
.ad.example.com = IDM.EXAMPLE.COM ad.example.com = IDM.EXAMPLE.COM
```

3. Replace both lines with an entry mapping the fully qualified domain name (FQDN) of the Linux clients in the Active Directory DNS zone to the IdM realm:

```
idm-client.ad.example.com = IDM.EXAMPLE.COM
```

By replacing the default mapping, you prevent Kerberos from sending its requests for the Active Directory domain to the IdM Kerberos Distribution Center (KDC). Instead Kerberos uses auto-discovery through SRV DNS records to locate the KDC.

25.7.2. Requesting SSL certificates without single sign-on

SSL-based services require a certificate with **dNSName** extension records that cover all system host names, because both original (A/AAAA) and CNAME records must be in the certificate. Currently, IdM only issues certificates to host objects in the IdM database.

In the described setup without single sign-on available, IdM already has a host object for the FQDN in the database, and **certmonger** can request a certificate using this name.

Prerequisites

• Installed and configured the IdM client by following the procedure in Configuring an IdM client without Kerberos single sign-on.

Procedure

• Use **certmonger** to request a certificate using the FQDN:

[root@idm-client.ad.example.com ~]# ipa-getcert request -r \

- -f /etc/httpd/alias/server.crt \
- -k /etc/httpd/alias/server.key \
- -N CN=ipa-client.ad.example.com \
- -D ipa-client.ad.example.com \
- -K host/idm-client.ad.example.com@IDM.EXAMPLE.COM \
- -U id-kp-serverAuth

The **certmonger** service uses the default host key stored in the /**etc/krb5.keytab** file to authenticate to the IdM Certificate Authority (CA).

25.7.3. Configuring an IdM client with Kerberos single sign-on

If you require Kerberos single sign-on to access resources on the IdM client, the client must be within the IdM DNS domain, for example **idm-client.idm.example.com**. You must create a CNAME record **idm-client.ad.example.com** in the Active Directory DNS domain pointing to the A/AAAA record of the IdM client.

For Kerberos-based application servers, MIT Kerberos supports a method to allow the acceptance of any host-based principal available in the application's keytab.

Procedure

 On the IdM client, disable the strict checks on what Kerberos principal is used to target the Kerberos server by setting the following option in the [libdefaults] section of the /etc/krb5.conf configuration file:

ignore_acceptor_hostname = true

25.7.4. Requesting SSL certificates with single sign-on

SSL-based services require a certificate with **dNSName** extension records that cover all system host names, because both original (A/AAAA) and CNAME records must be in the certificate. Currently, IdM only issues certificates to host objects in the IdM database.

This procedure describes how to to create a host object for **ipa-client.example.com** in IdM and make sure the real IdM machine's host object is able to manage this host.

Prerequisites

• You have disabled the strict checks on what Kerberos principal is used to target the Kerberos server as outlined in Configuring an IdM client with Kerberos single sign-on.

Procedure

- 1. Create a new host object on the IdM server:
 - [root@idm-server.idm.example.com ~]# ipa host-add idm-client.ad.example.com --force

Use the **--force** option, because the host name is a CNAME and not an A/AAAA record.

2. On the IdM server, allow the IdM DNS host name to manage the Active Directory host entry in the IdM database:

[root@idm-server.idm.example.com ~]# ipa host-add-managedby idm-client.ad.example.com

- --hosts=idm-client.idm.example.com
- 3. Your can now request an SSL certificate for your IdM client with the **dNSName** extension record for its host name within the Active Directory DNS domain:

[root@idm-client.idm.example.com ~]# ipa-getcert request -r \

- -f /etc/httpd/alias/server.crt \
- -k /etc/httpd/alias/server.key \
- -N CN=`hostname --fqdn` \
- -D `hostname --fqdn` \
- -D idm-client.ad.example.com \
- -K host/idm-client.idm.example.com@IDM.EXAMPLE.COM \
- -U id-kp-serverAuth

25.8. SETTING UP A TRUST

This section describes how to configure the Identity Management (IdM)/Active Directory (AD) trust on the IdM side using the command line.

Prerequisites

- DNS is correctly configured. Both IdM and AD servers must be able to resolve each other names. For details, see Configuring DNS and realm settings for a trust.
- Supported versions of AD and IdM are deployed. For details, see Supported versions of Windows Server.
- You have obtained a Kerberos ticket. For details, see Using kinit to log in to IdM manually .

25.8.1. Preparing the IdM server for the trust

Before you can establish a trust with AD, you must prepare the IdM domain using the **ipa-adtrust-install** utility on an IdM server.



NOTE

Any system where you run the **ipa-adtrust-install** command automatically becomes an AD trust controller. However, you must run **ipa-adtrust-install** only once on an IdM server.

Prerequisites

- IdM server is installed.
- You need root privileges to install packages and restart IdM services.

Procedure

- 1. Install the required packages:
 - [root@ipaserver ~]# yum install ipa-server-trust-ad samba-client
- 2. Authenticate as the IdM administrative user:
 - [root@ipaserver ~]# kinit admin
- 3. Run the **ipa-adtrust-install** utility:
 - [root@ipaserver ~]# ipa-adtrust-install

The DNS service records are created automatically if IdM was installed with an integrated DNS server.

If you installed IdM without an integrated DNS server, **ipa-adtrust-install** prints a list of service records that you must manually add to DNS before you can continue.

4. The script prompts you that the /etc/samba/smb.conf already exists and will be rewritten:

WARNING: The smb.conf already exists. Running ipa-adtrust-install will break your existing Samba configuration.

Do you wish to continue? [no]: yes

5. The script prompts you to configure the **slapi-nis** plug-in, a compatibility plug-in that allows older Linux clients to work with trusted users:

Do you want to enable support for trusted domains in Schema Compatibility plugin? This will allow clients older than SSSD 1.9 and non-Linux clients to work with trusted users.

Enable trusted domains support in slapi-nis? [no]: yes

6. When prompted, enter the NetBIOS name for the IdM domain or press **Enter** to accept the name suggested:

Trust is configured but no NetBIOS domain name found, setting it now. Enter the NetBIOS name for the IPA domain.

Only up to 15 uppercase ASCII letters, digits and dashes are allowed.

Example: EXAMPLE.

NetBIOS domain name [IDM]:

7. You are prompted to run the SID generation task to create a SID for any existing users:

Do you want to run the ipa-sidgen task? [no]: yes

This is a resource-intensive task, so if you have a high number of users, you can run this at another time.

8. **(Optional)** By default, the Dynamic RPC port range is defined as **49152-65535** for Windows Server 2008 and later. If you need to define a different Dynamic RPC port range for your environment, configure Samba to use different ports and open those ports in your firewall settings. The following example sets the port range to **55000-65000**.

[root@ipaserver ~]# net conf setparm global 'rpc server dynamic port range' 55000-65000

[root@ipaserver ~]# firewall-cmd --add-port=55000-65000/tcp [root@ipaserver ~]# firewall-cmd --runtime-to-permanent

9. Make sure that DNS is properly configured, as described in Verifying the DNS configuration for a trust.



IMPORTANT

Red Hat strongly recommends you verify the DNS configuration as described in Verifying the DNS configuration for a trust every time after running **ipa-adtrust-install**, especially if IdM or AD do not use integrated DNS servers.

10. Restart the **ipa** service:

[root@ipaserver ~]# ipactl restart

11. Use the **smbclient** utility to verify that Samba responds to Kerberos authentication from the IdM side:

[root@ipaserver ~]# **smbclient -L server.idm.example.com -k** lp load ex: changing to config backend registry

```
Sharename Type Comment
------
IPC$ IPC IPC Service (Samba 4.12.3)
...
```

25.8.2. Setting up a trust agreement using the command line

This section describes how to set up the trust agreement using the command line. The Identity Management (IdM) server allows you to configure three types of trust agreements:

- One-way trust default option. One-way trust enables Active Directory (AD) users and groups to access resources in IdM, but not the other way around. The IdM domain trusts the AD forest, but the AD forest does not trust the IdM domain.
- Two-way trust Two-way trust enables AD users and groups to access resources in IdM.
 You must configure a two-way trust for solutions such as Microsoft SQL Server that expect the
 S4U2Self and S4U2Proxy Microsoft extensions to the Kerberos protocol to work over a trust
 boundary. An application on a RHEL IdM host might request S4U2Self or S4U2Proxy
 information from an Active Directory domain controller about an AD user, and a two-way trust
 provides this feature.

Note that this two-way trust functionality does not allow IdM users to login to Windows systems, and the two-way trust in IdM does not give the users any additional rights compared to the one-way trust solution in AD.

- To create the two-way trust, add the following option to the command: --two-way=true
- External trust a trust relationship between IdM and an AD domain in different forests. While a
 forest trust always requires establishing a trust between IdM and the root domain of an Active
 Directory forest, an external trust can be established from IdM to a domain within a forest. This
 is only recommended if it is not possible to establish a forest trust between forest root domains
 due to administrative or organizational reasons.
 - To create the external trust, add the following option to the command: --external=true

In this section, the steps below shows you how to create a one-way trust agreement.

Prerequisites

- User name and password of a Windows administrator.
- You have prepared the IdM server for the trust.

Procedure

 Create a trust agreement for the AD domain and the IdM domain by using the ipa trust-add command:

[root@server ~]# ipa trust-add --type=ad ad_domain_name --admin ad_admin_username --password

25.8.3. Setting up a trust agreement in the IdM Web UI


This section describes how to configure the Identity Management (IdM)/Active Directory (AD) trust agreement on the IdM side using the IdM Web UI.

Prerequisites


- DNS is correctly configured. Both IdM and AD servers must be able to resolve each other names.
- Supported versions of AD and IdM are deployed.
- You have obtained a Kerberos ticket.
- Before creating a trust in the Web UI, prepare the IdM server for the trust as described in: Preparing the IdM server for the trust.
- You need to be logged in as an IdM administrator.

Procedure

- 1. Log in to the IdM Web UI with administrator privileges. For details, see Accessing the IdM Web UI in a web browser.
- 2. In the IdM Web UI, click the IPA Server tab.
- 3. In the IPA Server tab, click the Trusts tab.
- 4. In the drop down menu, select the **Trusts** option.




- 5. Click the Add button.
- 6. In the Add Trust dialog box, enter the name of the Active Directory domain.
- 7. In the **Account** and **Password** fields, add the administrator credentials of the Active Directory administrator.



- 8. [Optional] Select **Two-way trust**, if you want to enable AD users and groups to access resources in IdM. However, the two-way trust in IdM does not give the users any additional rights compared to the one-way trust solution in AD. Both solutions are considered equally secure because of default cross-forest trust SID filtering settings.
- 9. [Optional] If your domains are in different forests, select External trust.
- 10. Click Add.

If the trust has been successfully added to the IdM server, you can see the green pop-up window in the IdM Web UI. It means that the:

- Domain name exists
- User name and password of the Windows Server has been added correctly.



Now you can continue to test the trust connection and Kerberos authentication.

25.8.4. Verifying the Kerberos configuration

To verify the Kerberos configuration, test if it is possible to obtain a ticket for an Identity Management (IdM) user and if the IdM user can request service tickets.

Procedure

1. Request a ticket for an Active Directory (AD) user:

[root@ipaserver ~]# kinit user@AD.EXAMPLE.COM

2. Request service tickets for a service within the IdM domain:

[root@server ~]# kvno -S host server.idm.example.com

If the AD service ticket is successfully granted, there is a cross-realm ticket-granting ticket (TGT) listed with all of the other requested tickets. The TGT is named krbtqt/IPA.DOMAIN@AD.DOMAIN.

[root@server]# klist

Ticket cache: KEYRING:persistent:0:krb ccache hRtox00

Default principal: user@AD.EXAMPLE.COM

Valid starting Expires Service principal

03.05.2016 18:31:06 04.05.2016 04:31:01 host/server.idm.example.com@IDM.EXAMPLE.COM renew until 04.05.2016 18:31:00

03.05.2016 18:31:06 04.05.2016 04:31:01 krbtgt/IDM.EXAMPLE.COM@AD.EXAMPLE.COM renew until 04.05.2016 18:31:00

03.05.2016 18:31:01 04.05.2016 04:31:01 krbtgt/AD.EXAMPLE.COM@AD.EXAMPLE.COM renew until 04.05.2016 18:31:00

The **localauth** plug-in maps Kerberos principals to local System Security Services Daemon (SSSD) user names. This allows AD users to use Kerberos authentication and access Linux services, which support GSSAPI authentication directly.

25.8.5. Verifying the trust configuration on IdM

Before configuring trust, verify that the Identity Management (IdM) and Active Directory (AD) servers can resolve themselves and each other.

Prerequisites

• You need to be logged in with administrator privileges.

Procedure

1. Run a DNS query for the MS DC Kerberos over UDP and LDAP over TCP service records.

[root@server ~]# dig +short -t SRV _kerberos._udp.dc._msdcs.idm.example.com. 0 100 88 server.idm.example.com.

[root@server ~]# dig +short -t SRV _ldap._tcp.dc._msdcs.idm.example.com. 0 100 389 server.idm.example.com.

These commands list all IdM servers on which **ipa-adtrust-install** has been executed. The output is empty if **ipa-adtrust-install** has not been executed on any IdM server, which is typically before establishing the first trust relationship.

2. Run a DNS query for the Kerberos and LDAP over TCP service records to verify that IdM is able to resolve service records for AD:

```
[root@server ~]# dig +short -t SRV _kerberos._tcp.dc._msdcs.ad.example.com. 0 100 88 addc1.ad.example.com.

[root@ipaserver ~]# dig +short -t SRV _ldap._tcp.dc._msdcs.ad.example.com. 0 100 389 addc1.ad.example.com.
```

.

25.8.6. Verifying the trust configuration on AD

After configuring the trust, verify that:

- The Identity Management (IdM)-hosted services are resolvable from the Active Directory (AD) server.
- AD services are resolvable from the AD server.

Prerequisites

• You need to be logged in with administrator privileges.

Procedure

1. On the AD server, set the **nslookup.exe** utility to look up service records.

```
C:\>nslookup.exe
> set type=SRV
```

2. Enter the domain name for the Kerberos over UDP and LDAP over TCP service records.

```
> _kerberos._udp.idm.example.com.
_kerberos._udp.idm.example.com. SRV service location:
           = 0
  priority
                = 100
  weight
  port
               = 88
  svr hostname = server.idm.example.com
> _ldap._tcp.idm.example.com
_ldap._tcp.idm.example.com
                            SRV service location:
                = 0
  priority
  weight
                 = 100
                = 389
  svr hostname = server.idm.example.com
```

3. Change the service type to TXT and run a DNS query for the TXT record with the IdM Kerberos realm name.

```
C:\>nslookup.exe
> set type=TXT
> _kerberos.idm.example.com.
_kerberos.idm.example.com. text =

"IDM.EXAMPLE.COM"
```

4. Run a DNS query for the MS DC Kerberos over UDP and LDAP over TCP service records.

```
C:\>nslookup.exe
> set type=SRV
> _kerberos._udp.dc._msdcs.idm.example.com.
_kerberos._udp.dc._msdcs.idm.example.com.
                                               SRV service location:
  priority = 0
  weight = 100
  port = 88
  svr hostname = server.idm.example.com
> Idap. tcp.dc. msdcs.idm.example.com.
ldap. tcp.dc. msdcs.idm.example.com.
                                          SRV service location:
  priority = 0
  weight = 100
  port = 389
  svr hostname = server.idm.example.com
```

Active Directory only expects to discover domain controllers that can respond to AD-specific protocol requests, such as other AD domain controllers and IdM trust controllers. Use the **ipa-adtrust-install** tool to promote an IdM server to a trust controller, and you can verify which servers are trust controllers with the **ipa server-role-find --role 'AD trust controller'** command.

5. Verify that AD services are resolvable from the AD server.

```
C:\>nslookup.exe
> set type=SRV
```

6. Enter the domain name for the Kerberos over UDP and LDAP over TCP service records.

```
> _kerberos._udp.dc._msdcs.ad.example.com.
    _kerberos._udp.dc._msdcs.ad.example.com. SRV service location:
    priority = 0
    weight = 100
    port = 88
    svr hostname = addc1.ad.example.com
> _ldap._tcp.dc._msdcs.ad.example.com.
    _ldap._tcp.dc._msdcs.ad.example.com. SRV service location:
    priority = 0
    weight = 100
    port = 389
    svr hostname = addc1.ad.example.com
```

25.8.7. Creating a trust agent

A trust agent is an IdM server that can perform identity lookups against AD domain controllers.

For example, if you are creating a replica of an IdM server that has a trust with Active Directory, you can set up the replica as a trust agent. A replica does not automatically have the AD trust agent role installed.

Prerequisites

- IdM is installed with an Active Directory trust.
- The **sssd-tools** package is installed.

Procedure

1. On an existing trust controller, run the **ipa-adtrust-install --add-agents** command:

[root@existing_trust_controller]# ipa-adtrust-install --add-agents

The command starts an interactive configuration session and prompts you for the information required to set up the agent.

2. Restart the IdM service on the trust agent.

```
[root@new_trust_agent]# ipactl restart
```

3. Remove all entries from the SSSD cache on the trust agent:

```
[root@new_trust_agent]# sssctl cache-remove
```

4. Verify that the replica has the AD trust agent role installed:.

```
[root@existing_trust_controller]# ipa server-show new_replica.idm.example.com ...
Enabled server roles: CA server, NTP server, AD trust agent
```

Additional resources

- For further information about the **--add-agents** option, see the **ipa-adtrust-install(1)** man page.
- For more information on trust agents, see Trust controllers and trust agents in the Planning Identity Management guide.

25.9. REMOVING THE TRUST USING THE COMMAND LINE

This section describes how to remove the Identity Management (IdM)/Active Directory (AD) trust on the IdM side using the command line interface.

Prerequisites

• You have obtained a Kerberos ticket as an IdM administrator. For details, see Logging in to IdM in the Web UI: Using a Kerberos ticket.

Procedure

1. Use the **ipa trust-del** command to remove the trust configuration from IdM.

```
[root@server ~]# ipa trust-del ad_domain_name
------
Deleted trust "ad_domain_name"
------
```

2. Remove the trust object from your Active Directory configuration.

Verification steps

Use the ipa trust-show command to confirm that the trust has been removed.

[root@server ~]# ipa trust-show ad.example.com ipa: ERROR: ad.example.com: trust not found

25.10. REMOVING THE TRUST USING THE IDM WEB UI


This section describes how to remove the Identity Management (IdM)/Active Directory (AD) trust using the IdM Web UI.

Prerequisites


 You have obtained a Kerberos ticket. For details, see Logging in to IdM in the Web UI: Using a Kerberos ticket.

Procedure


- 1. Log in to the IdM Web UI with administrator privileges. For details, see Accessing the IdM Web UI in a web browser.
- 2. In the IdM Web UI, click the IPA Server tab.
- 3. In the **IPA Server** tab, click the **Trusts** tab.
- 4. Select the trust you want to remove.



- 5. Click the **Delete** button.
- 6. In the Remove trusts dialog box, click Delete.



If the trust is successfully deleted, the Web UI displays a green pop-up with the text:



1. Remove the trust object from your Active Directory configuration.

PART III. MIGRATING IDM FROM RHEL 7 TO RHEL 8 AND KEEPING IT UP-TO-DATE

CHAPTER 26. MIGRATING YOUR IDM ENVIRONMENT FROM RHEL 7 SERVERS TO RHEL 8 SERVERS

To upgrade a RHEL 7 IdM environment to RHEL 8, you must first add new RHEL 8 IdM replicas to your RHEL 7 IdM environment, and then retire the RHEL 7 servers.



WARNING

Performing an in-place upgrade of RHEL 7 IdM servers to RHEL 8 is not supported.

This section describes how to **migrate** all Identity Management (IPA) data and configuration from a Red Hat Enterprise Linux (RHEL) 7 server to a RHEL 8 server.

The migration procedure includes:

- 1. Configuring a RHEL 8 IdM server and adding it as a replica to your current RHEL 7 IdM environment. For details, see Installing the RHEL 8 Replica.
- 2. Making the RHEL 8 server the certificate authority (CA) renewal server. For details, see Assigning the CA renewal server role to the RHEL 8 IdM server.
- 3. Stopping the generation of the certificate revocation list (CRL) on the RHEL 7 server and redirecting CRL requests to RHEL 8. For details, see Stopping CRL generation on a RHEL 7 IdM CA server.
- 4. Starting the generation of the CRL on the RHEL 8 server. For details, see Starting CRL generation on the new RHEL 8 IdM CA server.
- 5. Stopping and decommissioning the original RHEL 7 CA renewal server. For details, see Stopping and decommissioning the RHEL 7 server.

In the following procedures:

- **rhel8.example.com** is the RHEL 8 system that will become the new CA renewal server.
- **rhel7.example.com** is the original RHEL 7 CA renewal server. To identify which Red Hat Enterprise Linux 7 server is the CA renewal server, run the following command on any IdM server:

[root@rhel7 ~]# ipa config-show | grep "CA renewal" IPA CA **renewal** master: rhel7.example.com

If your IdM deployment is CA-less, any IdM server running on RHEL 7 can be **rhel7.example.com**.



Complete the steps in the following sections **only** if your IdM deployment uses an embedded certificate authority (CA):

- Assigning the CA renewal server role to the RHEL 8 IdM server
- Stopping CRL generation on a RHEL 7 IdM CA server.
- Starting CRL generation on the new RHEL 8 IdM CA server

26.1. PREREQUISITES FOR MIGRATING IDM FROM RHEL 7 TO 8

On rhel7.example.com:

- 1. Upgrade the system to the latest RHEL 7 version.
- 2. Ensure that the domain level for your domain is set to 1. For more information, see Displaying and Raising the Domain Level in the *Linux Domain Identity, Authentication, and Policy Guide* for RHEL 7.
- 3. Update the **ipa-*** packages to their latest version:

[root@rhel7 ~]# dnf update ipa-*



WARNING

When upgrading multiple Identity Management (IdM) servers, wait at least 10 minutes between each upgrade.

When two or more servers are upgraded simultaneously or with only short intervals between the upgrades, there is not enough time to replicate the post-upgrade data changes throughout the topology, which can result in conflicting replication events.

On rhel8.example.com:

- 1. The latest version of Red Hat Enterprise Linux is installed on the system. For more information, see Performing a standard RHEL installation.
- 2. Ensure the system is an IdM client enrolled into the domain for which **rhel7.example.com** IdM server is authoritative. For more information, see Installing an IdM client: Basic scenario.
- 3. Ensure the system meets the requirements for IdM server installation.
- 4. Ensure the system uses a time server that is synchronized with **rhel7.example.com**.



In RHEL 8, IdM does not provide its own time server: the installation of IdM on **rhel8.example.com** does not result in the installation of an NTP server on the host.

- 5. Ensure the system is authorized for the installation of an IdM replica .
- 6. Update the **ipa-*** packages to their latest version:

[root@rhel7 ~]# dnf update ipa-*

Additional resources

- To decide which server roles you want to install on the new IdM primary server, **rhel8.example.com**, see the following links:
 - For details on the CA server role in IdM, see Planning your CA services.
 - For details on the DNS server role in IdM, see Planning your DNS services and host names .
 - For details on integration based on cross-forest trust between an IdM and Active Directory (AD), see Indirect integration.
- To be able to install specific server roles for IdM in RHEL 8, you need to download packages from specific IdM module streams: Installing packages required for an IdM server.
- To upgrade a system from RHEL 7 to RHEL 8, see Upgrading from RHEL 7 to RHEL 8.

26.2. INSTALLING THE RHEL 8 REPLICA

1. List which server roles are present in your RHEL 7 environment:

[root@rhel7 ~]# ipa server-role-find --status enabled

4 server roles matched

Server name: rhel7.example.com

Role name: CA server Role status: enabled

Server name: replica7.example.com

Role name: DNS server Role status: enabled

Server name: rhel7.example.com

Role name: DNS server Role status: enabled

Server name: rhel7.example.com

Role name: NTP server Role status: enabled [... output truncated ...]

- 2. Install the IdM server on **rhel8.example.com** as a replica of the IdM RHEL 7 server, including all the server roles present on your **rhel7.example.com** except the NTP server role. To install the roles from the example above, use these options with the **ipa-replica-install** command:
 - --setup-ca to set up the Certificate System component
 - **--setup-dns** and **--forwarder** to configure an integrated DNS server and set a forwarder to take care of DNS queries that go outside the IdM domain



Additionally, if your IdM deployment is in a trust relationship with Active Directory (AD), add the **--setup-adtrust** option to the **ipa-replica-install** command to configure AD trust capability on **rhel8.example.com**.

To set up an IdM server with the IP address of 192.0.2.1 that uses a global forwarder with the IP address of 192.0.2.20:

[root@rhel8 ~]# ipa-replica-install --setup-ca --ip-address 192.0.2.1 --setup-dns --forwarder 192.0.2.20

Global forwarders are DNS servers used for resolving all DNS queries for which an IdM server is not authoritative.

You do not need to specify the RHEL 7 IdM server because if DNS is working correctly, **rhel8.example.com** will find it using DNS autodiscovery.

3. After the installation completes, verify that the IdM services are running on **rhel8.example.com**:

[root@rhel8 ~]# ipactl status Directory Service: RUNNING [... output truncated ...]

ipa: INFO: The ipactl command was successful

4. Verify that **rhel7.example.com** and **rhel8.example.com** are both configured as certificate authority (CA) servers:

[root@rhel8 ~]\$ kinit admin [root@rhel8 ~]\$ ipa-csreplica-manage list

rhel7.example.com: master rhel8.example.com: master

5. Optionally, to display details about the replication agreement between **rhel7.example.com** and **rhel8.example.com**:

[root@rhel8 ~]# ipa-csreplica-manage list --verbose rhel8.example.com Directory Manager password:

rhel7.example.com last init status: None

last init ended: 1970-01-01 00:00:00+00:00

last update status: Error (0) Replica acquired successfully: Incremental update succeeded

last update ended: 2019-02-13 13:55:13+00:00

6. Optionally, add an _ntp._udp service (SRV) record for your external NTP time server to the DNS of the newly-installed IdM server, rhel8.example.com. Doing this is recommended because IdM in RHEL 8 does not provide its own time service. The presence of the SRV record for the time server in IdM DNS ensures that future RHEL 8 replica and client installations are automatically configured to synchronize with the time server used by rhel8.example.com. This is because ipa-client-install looks for the _ntp._udp DNS entry unless --ntp-server or --ntp-pool options are provided on the install command-line interface (CLI).

26.3. ASSIGNING THE CA RENEWAL SERVER ROLE TO THE RHEL 8 IDM SERVER



NOTE

Complete the steps in this section only if your IdM deployment uses an embedded certificate authority (CA).

On **rhel8.example.com**, configure **rhel8.example.com** as the new CA renewal server:

• Configure **rhel8.example.com** to handle CA subsystem certificate renewal:

[root@rhel8 ~]# ipa config-mod --ca-renewal-master-server rhel8.example.com

...

IPA masters: rhel7.example.com, rhel8.example.com IPA CA servers: rhel7.example.com, rhel8.example.com IPA NTP servers: rhel7.example.com, rhel8.example.com

IPA CA renewal master: rhel8.example.com

The output confirms that the update was successful.

26.4. STOPPING CRL GENERATION ON A RHEL 7 IDM CA SERVER



NOTE

Complete the steps in this section only if your IdM deployment uses an embedded certificate authority (CA).

This section describes how to stop generating the Certificate Revocation List (CRL) on the rhel7.example.com CA server using the **ipa-crlgen-manage** command.

Prerequisites

• You must be logged in as root.

Procedure

1. Optionally, check if **rhel7.example.com** is generating the CRL:

[root@rhel7 ~]# ipa-crlgen-manage status

CRL generation: enabled

Last CRL update: 2019-10-31 12:00:00

Last CRL Number: 6

The ipa-crlgen-manage command was successful

2. Stop generating the CRL on the **rhel7.example.com** server:

[root@rhel7 ~]# ipa-crlgen-manage disable

Stopping pki-tomcatd

Editing /var/lib/pki/pki-tomcat/conf/ca/CS.cfg

Starting pki-tomcatd

Editing /etc/httpd/conf.d/ipa-pki-proxy.conf

Restarting httpd

CRL generation disabled on the local host. Please make sure to configure CRL generation on another master with ipa-crigen-manage enable.

The ipa-crlgen-manage command was successful

3. Optionally, check if the **rhel7.example.com** server stopped generating the CRL:

[root@rhel7 ~]# ipa-crlgen-manage status

The **rhel7.example.com** server stopped generating the CRL. The next step is to enable generating the CRL on **rhel8.example.com**.

26.5. STARTING CRL GENERATION ON THE NEW RHEL 8 IDM CA SERVER



NOTE

Complete the steps in this section only if your IdM deployment uses an embedded certificate authority (CA).

Prerequisites

• You must be logged in as root on the rhel8.example.com machine.

Procedure

1. To start generating CRL on rhel8.example.com, use the ipa-crigen-manage enable command:

[root@rhel8 ~]# ipa-crlgen-manage enable

Stopping pki-tomcatd

Editing /var/lib/pki/pki-tomcat/conf/ca/CS.cfg

Starting pki-tomcatd

Editing /etc/httpd/conf.d/ipa-pki-proxy.conf

Restarting httpd

Forcing CRL update

CRL generation enabled on the local host. Please make sure to have only a single CRL generation master.

The ipa-crigen-manage command was successful

2. To check if CRL generation is enabled, use the **ipa-crlgen-manage status** command:

[root@rhel8 ~]# ipa-crlgen-manage status

CRL generation: enabled

Last CRL update: 2019-10-31 12:10:00

Last CRL Number: 7

The ipa-crlgen-manage command was successful

_

26.6. STOPPING AND DECOMMISSIONING THE RHEL 7 SERVER

- 1. Make sure that all data, including the latest changes, have been correctly migrated from **rhel7.example.com** to **rhel8.example.com**. For example:
 - a. Add a new user on rhel7.example.com:

[root@rhel7 ~]# **ipa user-add** *random_user* First name: random Last name: user

b. Check that the user has been replicated to **rhel8.example.com**:

[root@rhel8 ~]# ipa user-find random_user

1 user matched
----User login: random_user
First name: random
Last name: user

2. Stop all IdM services on **rhel7.example.com** to force domain discovery to the new **rhel8.example.com** server.

```
[root@rhel7 ~]# ipactl stop
Stopping CA Service
Stopping pki-ca:
                                       [ OK ]
Stopping HTTP Service
Stopping httpd:
                                       [ OK ]
Stopping MEMCACHE Service
Stopping ipa memcached:
                                            [ OK ]
Stopping DNS Service
Stopping named: .
                                        [ OK ]
Stopping KPASSWD Service
Stopping Kerberos 5 Admin Server:
                                               [ OK ]
Stopping KDC Service
Stopping Kerberos 5 KDC:
                                            [ OK ]
Stopping Directory Service
Shutting down dirsrv:
  EXAMPLE-COM...
                                          [ OK ]
  PKI-IPA...
                                     [ OK ]
```

After this, the **ipa** utility will contact the new server through a remote procedure call (RPC).

3. Remove the RHEL 7 server from the topology by executing the removal commands on the RHEL 8 server. For details, see Chapter 8, *Uninstalling an IdM server*.

CHAPTER 27. UPDATING AND DOWNGRADING IDM

You can use the **yum** utility to update the Identity Management (IdM) packages on the system.

• To update all IdM packages that are relevant for your profile and that have updates available:

yum upgrade ipa-*

 Alternatively, to install or update packages to match the latest version available for your profile from any enabled repository:

yum distro-sync ipa-*

After you update the IdM packages on at least one server, all other servers in the topology receive the updated schema, even if you do not update their packages. This ensures that any new entries which use the new schema can be replicated among the other servers.



WARNING

When updating multiple IdM servers, wait at least 10 minutes after updating one server before updating another server. However, the actual time required for a server's successful update depends on the topology deployed, the latency of the connections, and the number of changes generated by the update.

When two or more servers are updated simultaneously or with only short intervals between the upgrades, there is not enough time to replicate the post-upgrade data changes throughout the topology, which can result in conflicting replication events.

Downgrading IdM packages manually is not supported. Use **yum distro-sync** to update and downgrade packages in modules.



IMPORTANT

Do not run the **yum downgrade** command on any of the **ipa-*** packages.

Related information

• For details on using the **yum** utility, see the **yum(8)** manual pages.

CHAPTER 28. UPGRADING AN IDM CLIENT FROM RHEL 7 TO RHEL 8

Unlike IdM servers, performing an in-place upgrade of an IdM client from RHEL 7 to RHEL 8 is supported.

In RHEL 8, some uncommon options and unused functionality have been removed from the System Security Services Daemon (SSSD), the service responsible for authentication in an IdM environment. See the following sections for steps to remove those options.

- Updating the SSSD configuration after upgrading to RHEL 8
- List of SSSD functionality removed in RHEL 8

28.1. UPDATING THE SSSD CONFIGURATION AFTER UPGRADING TO RHEL 8

After upgrading an Identity Management (IdM) client from Red Hat Enterprise Linux (RHEL) 7 to RHEL 8, the **leapp** upgrade application might display a warning that some SSSD configuration options are no longer supported.

The following procedures describe how to update your SSSD configuration to address these issues.

Prerequisites

- You have upgraded an IdM client from RHEL 7 to RHEL 8.
- You have **root** permissions to edit /**etc/sssd/sssd.conf**.

28.1.1. Switching from the local ID provider to the files ID provider

If you see the following error, replace the **local** ID provider with the **files** ID provider:

SSSD Domain "example.com": local provider is no longer supported and the domain will be ignored. **Local provider is no longer supported.**

Procedure

- Ensure any users and groups you retrieved with the local ID provider are also in the /etc/passwd and /etc/group files. This ensures that the files provider can access those users and groups.
 - a. If you need to create users, use the **useradd** command. If you need to specify the UID, add the **-u** option:
 - [root@client ~]# useradd -u 3001 username
 - b. If you need to create groups, use the **groupadd** command. If you need to specify the GID, add the **-g** option:

[root@client ~]# groupadd -g 5001 groupname

- 2. Open the /etc/sssd/sssd.conf configuration file in a text editor.
- 3. Replace id_provider=local with id_provider=files.

```
[domain/example.com]
id_provider = files
...
```

- 4. Save the /etc/sssd/sssd.conf configuration file.
- 5. Restart SSSD to load the configuration changes.

[root@client ~]# systemctl restart sssd

28.1.2. Removing deprecated options

If you see either of the following errors regarding deprecated options, Red Hat recommends removing those options from the /etc/sssd/sssd.conf configuration file:

SSSD Domain "example.com": option ldap_groups_use_matching_rule_in_chain has no longer any effect

Option Idap groups use matching rule in chain was removed and it will be ignored.

SSSD Domain "example.com": option **ldap_initgroups_use_matching_rule_in_chain** has no longer any effect

Option Idap_initgroups_use_matching_rule_in_chain was removed and it will be ignored.

Procedure

- 1. Open the /etc/sssd/sssd.conf configuration file in a text editor.
- 2. Remove any occurrences of **Idap_groups_use_matching_rule_in_chain** or **Idap_initgroups_use_matching_rule_in_chain** options.
- 3. Save the /etc/sssd/sssd.conf configuration file.
- 4. Restart SSSD to load the configuration changes.

[root@client ~]# systemctl restart sssd

28.1.3. Enabling wildcard matching for sudo rules

The following warning indicates that **sudo** rules with wildcards in them will not work by default in RHEL 8, as the **ldap_sudo_include_regexp** option is now set to **false** by default.

SSSD Domain "example.com": sudo rules containing wildcards will stop working.

Default value of Idap_sudo_include_regexp changed from true to false for performance reason.

If you use **sudo** rules with wildcards and want to enable wildcard matching, manually set the **ldap sudo include regexp** option to **true**.



Red Hat recommends against using wildcards to match **sudo** rules.

If the **Idap_sudo_include_regexp** option is set to **true**, SSSD downloads every **sudo** rule that contains a wildcard in the **sudoHost** attribute, which negatively impacts LDAP search performance.

Procedure

- 1. Open the /etc/sssd/sssd.conf configuration file in a text editor.
- 2. In the example.com domain, set Idap_sudo_include_regexp=true.

```
[domain/example.com]
...
Idap_sudo_include_regexp = true
...
```

- 3. Save the /etc/sssd/sssd.conf configuration file.
- 4. Restart SSSD to load the configuration changes.

[root@client ~]# systemctl restart sssd

28.2. LIST OF SSSD FUNCTIONALITY REMOVED IN RHEL 8

The following SSSD functionality has been removed in RHEL 8.

The local ID provider has been removed

The **local** ID provider, used to serve user information from the local SSSD cache, was deprecated in RHEL 7 and is no longer supported in RHEL 8. If you have a domain with **id_provider=local** in your **/etc/sssd/sssd.conf** configuration, SSSD ignores this domain and starts normally.

Command line tools to manage users and groups inlocal domains have been removed

The following commands, which only affected local domains, have been removed:

- sss_useradd
- sss userdel
- sss_groupadd
- sss_groupdel

Support for the Idap_groups_use_matching_rule_in_chain option has been removed

This Active Directory-specific option does not provide a significant performance benefit and is ignored in any RHEL 8 **sssd.conf** configuration.

Support for the dap_initgroups_use_matching_rule_in_chain option has been removed

This Active Directory-specific option does not provide a significant performance benefit and is ignored in any RHEL 8 **sssd.conf** configuration.

The Idap_sudo_include_regexp option now defaults to false

In RHEL 7, this option was set to **true** by default. If this option is set to **true**, SSSD downloads every **sudo** rule that contains a wildcard in the **sudoHost** attribute, which negatively impacts LDAP search performance.

The **sssd-secrets** responder has been removed

As the Kerberos Cache Manager (KCM) no longer relies on the **sssd-secrets** responder, and no other IdM process uses it, it has been removed.

28.3. ADDITIONAL RESOURCES

• For more details on upgrading to RHEL 8, see Upgrading from RHEL 7 to RHEL 8.