

请现场的同学们:

1. 打开雨课堂,点击页面右下角喇叭按钮调至静音状态

本次课程是

线上+线下

融合式教学

请远程上课的同学们:

- 1. 打开雨课堂,点击页面右下角喇 叭按钮调至静音状态
- 2. 打开"腾讯会议" (会议室:824 8461 5333) , 进入会议室,并关闭麦克风

CHAPTER 5: PROCEDURES

What's Next

- Stack Operations
- Defining and Using Procedures
- Linking to an External Library
- The Irvine32 Library
- Program Design Using Procedures
- 64-Bit Assembly Programming

When not to push a register

The sum of the three registers is stored in EAX on line (3), but the POP instruction replaces it with the starting value of EAX on line (4):

```
SumOf PROC ; sum of three integers
push eax ; 1
add eax,ebx ; 2
add eax,ecx ; 3
pop eax ; 4
ret
SumOf ENDP
```

What's Next

- Stack Operations
- Defining and Using Procedures
- Linking to an External Library
- The Irvine32 Library
- Program Design Using Procedures
- 64-Bit Assembly Programming


What is a Link Library?

- A file containing procedures that have been compiled into machine code
 - constructed from one or more OBJ files
- To build a library, . . .
 - start with one or more ASM source files
 - assemble each into an OBJ file
 - create an empty library file (extension .LIB)
 - add the OBJ file(s) to the library file, using the Microsoft LIB utility

Take a quick look at Irvine32.asm

How The Linker Works

- Your programs link to Irvine32.lib using the linker command inside a batch file named make32.bat.
- Notice the two LIB files: Irvine32.lib, and kernel32.lib
 - the latter is part of the Microsoft Win32 Software Development Kit (SDK)





Calling Irvine32 Library Procedure

- Call each procedure using the CALL instruction.
 - Some procedures require input arguments.
 - The INCLUDE directive copies in the procedure prototypes (declarations).
- The following example displays "1234" on the console:

```
INCLUDE Irvine32.inc
.code
mov eax,1234h ; input argument
call WriteHex ; show hex number
call Crlf ; end of line
```

What's Next

- Stack Operations
- Defining and Using Procedures
- Linking to an External Library
- The Irvine32 Library
- Program Design Using Procedures
- 64-Bit Assembly Programming

Program Design Using Procedures

- Top-Down Design (functional decomposition) involves the following:
 - design your program before starting to code
 - break large tasks into smaller ones
 - use a hierarchical structure based on procedure calls
 - test individual procedures separately

What's Next

- Stack Operations
- Defining and Using Procedures
- Linking to an External Library
- The Irvine32 Library
- Program Design Using Procedures
- 64-Bit Assembly Programming

64-Bit Assembly Programming

- The Irvine64 Library
- Calling 64-Bit Subroutines
- The x64 Calling Convention

Calling 64-Bit Subroutines

- Place the first four parameters in registers
- Add PROTO directives at the top of your program
 - examples:

```
ExitProcess PROTO ; located in the Windows API WriteHex64 PROTO ; located in the Irvine64 library
```

The x64 Calling Convention

- Must use this with the 64-bit Windows API
- CALL instruction subtracts 8 from RSP
- First four parameters must be placed in RCX, RDX, R8, and R9
- Caller must allocate at least 32 bytes of shadow space on the stack
- When calling a subroutine, the stack pointer must be aligned on a 16-byte boundary.

See the CallProc_64.asm example program.

CHAPTER 6: CONDITIONAL PROCESSING

Chapter Overview

- Boolean and Comparison Instructions
- Conditional Jumps
- Conditional Loop Instructions
- Conditional Structures
- Application: Finite-State Machines
- Conditional Control Flow Directives

Boolean and Comparison Instructions

- CPU Status Flags
- AND Instruction
- OR Instruction
- XOR Instruction
- NOT Instruction
- Applications
- TEST Instruction
- CMP Instruction


Status Flags - Review

- The Zero flag is set when the result of an operation equals zero.
- The Carry flag is set when an instruction generates a result that is too large (or too small) for the destination operand.
- The Sign flag is set if the destination operand is negative, and it is clear if the destination operand is positive.
- The Overflow flag is set when an instruction generates an invalid signed result.
- The Parity flag is set when an instruction generates an even number of 1 bits in the low byte of the destination operand.
- The Auxiliary Carry flag is set when an operation produces a carry out from bit 3 to bit 4

AND Instruction

- Performs a Boolean AND operation between each pair of matching bits in two operands
- Syntax:

AND destination, source (same operand types as MOV)



AND

Х	у	x ∧ y
0	0	0
0	1	0
1	0	0
1	1	1

OR Instruction

- Performs a Boolean OR operation between each pair of matching bits in two operands
- Syntax:

OR destination, source

00111011 OR 00001111 unchanged 0011111 set OR

х	у	x ∨ y
0	0	0
0	1	1
1	0	1
1	1	1

XOR Instruction

- Performs a Boolean exclusive-OR operation between each pair of matching bits in two operands
- Syntax:

XOR destination, source

00111011 XOR 00001111 unchanged 00110100 inverted **XOR**

х	у	x ⊕ y
0	0	0
0	1	1
1	0	1
1	1	0


XOR is a useful way to toggle (invert) the bits in an operand.

NOT Instruction

- Performs a Boolean NOT operation on a single destination operand
- Syntax:

NOT destination


NOT 00111011 11000100 inverted NOT



Bit-Mapped Sets

- Binary bits indicate set membership
- Efficient use of storage
- Also known as bit vectors

Figure 6-1 Mapping Binary Bits to an Array.



Bit-Mapped Set Operations

- Set Complement
 - mov eax,setX
 - not eax
- Set Intersection
 - mov eax,setX
 - and eax,setY
- Set Union
 - mov eax,setX
 - or eax,setY

TEST Instruction

- Performs a nondestructive (非破坏性的) AND operation between each pair of matching bits in two operands
- No operands are modified, but the Zero flag is affected.
- Example: jump to a label if neither bit 0 nor bit 1 in AL is set.

```
test al,00000011b
jz ValueNotFound
```

Example: jump to a label if either bit 0 or bit 1 in AL is set.

```
test al,00000011b
jnz ValueFound
```

CMP Instruction

- Compares the destination operand to the source operand
 - Nondestructive subtraction of source from destination (destination operand is not changed)
- Syntax: CMP destination, source
- Example: destination == source

```
mov al,5
cmp al,5
; Zero flag set
```

Example: destination < source

```
mov al,4
cmp al,5
; Carry flag set
```

What's Next

- Boolean and Comparison Instructions
- Conditional Jumps
- Conditional Loop Instructions
- Conditional Structures
- Application: Finite-State Machines
- Conditional Control Flow Directives

Conditional Jumps

- Jumps Based On . . .
 - Specific flags
 - Equality
 - Unsigned comparisons
 - Signed Comparisons
- Applications
- Encrypting a String
- Bit Test (BT) Instruction

Jcond Instruction

 A conditional jump instruction branches to a label when specific register or flag conditions are met

Examples:

- JC, JB jump to a label if the Carry flag is set
- JZ, JE jump to a label if the Zero flag is set
- JS jumps to a label if the Sign flag is set
- JNZ, JNE jump to a label if the Zero flag is clear
- JECXZ jumps to a label if ECX equals 0

Jcond Ranges

- Prior to the 386:
 - jump must be within –128 to +127 bytes from current location counter
- x86 processors:
 - 32-bit offset permits jump anywhere in memory

Offset	Encodin	g	ASM Source
0040101A	B0 80	mov al,80h L'	1: mov al, -128
0040101C	3C 0A	cmp al,0Ah	cmp al, 10
0040101E	74 FA	je L1 (40101Ah	jz L1
00401020	8A D8	mov bl,al	mov bl, al
F	4: - 6	0040102	0
		+ FFFFFFF	A
		0040101	A

Jumps Based on Specific Flags

Mnemonic	Description	Flags
JZ	Jump if zero	ZF = 1
JNZ	Jump if not zero	ZF = 0
JC	Jump if carry	CF = 1
JNC	Jump if not carry	CF = 0
JO	Jump if overflow	OF = 1
JNO	Jump if not overflow	OF = 0
JS	Jump if signed	SF = 1
JNS	Jump if not signed	SF = 0
JP	Jump if parity (even)	PF = 1
JNP	Jump if not parity (odd)	PF = 0

Jumps Based on Equality

Mnemonic	Description
JE	Jump if equal $(leftOp = rightOp)$
JNE	Jump if not equal ($leftOp \neq rightOp$)
JCXZ	Jump if $CX = 0$
JECXZ	Jump if ECX = 0

Jumps Based on Unsigned Comparisons

Mnemonic	Description
JA	Jump if above (if $leftOp > rightOp$)
JNBE	Jump if not below or equal (same as JA)
JAE	Jump if above or equal (if $leftOp >= rightOp$)
JNB	Jump if not below (same as JAE)
JВ	Jump if below (if $leftOp < rightOp$)
JNAE	Jump if not above or equal (same as JB)
JBE	Jump if below or equal (if $leftOp \le rightOp$)
JNA	Jump if not above (same as JBE)

Jumps Based on Signed Comparisons

Mnemonic	Description
JG	Jump if greater (if leftOp > rightOp)
JNLE	Jump if not less than or equal (same as JG)
JGE	Jump if greater than or equal (if $leftOp >= rightOp$)
JNL	Jump if not less (same as JGE)
JL	Jump if less (if $leftOp < rightOp$)
JNGE	Jump if not greater than or equal (same as JL)
JLE	Jump if less than or equal (if $leftOp \le rightOp$)
JNG	Jump if not greater (same as JLE)

Applications

- Task: Jump to label Larger if unsigned EAX is greater than EBX
- Solution: Use CMP, followed by JA

```
cmp eax,ebx
ja Larger
```

- Task: Jump to label Greater if signed EAX is greater than EBX
- Solution: Use CMP, followed by JG

```
cmp eax,ebx
jg Greater
```

BT (Bit Test) Instruction

- Copies bit n from an operand into the Carry flag
- Syntax: BT bitBase, n
 - bitBase may be r/m16 or r/m32
 - n may be *r16, r32*, or *imm8*
- Example: jump to label L1 if bit 9 is set in the AX register:

```
bt AX,9 ; CF = bit 9
jc L1 ; jump if Carry
```

What's Next

- Boolean and Comparison Instructions
- Conditional Jumps
- Conditional Loop Instructions
- Conditional Structures
- Application: Finite-State Machines
- Conditional Control Flow Directives

Conditional Loop Instructions

- LOOPZ and LOOPE
- LOOPNZ and LOOPNE

LOOPZ and LOOPE

Syntax:

LOOPE destination LOOPZ destination

- Logic:
 - ECX ← ECX 1
 - if ECX > 0 and ZF=1, jump to destination
- Useful when scanning an array for the first element that does not match a given value.

In 32-bit mode, ECX is the loop counter register. In 16-bit real-address mode, CX is the counter, and in 64-bit mode, RCX is the counter.

LOOPNZ and LOOPNE

- LOOPNZ (LOOPNE) is a conditional loop instruction
- Syntax:

LOOPNZ destination LOOPNE destination

- Logic:
 - ECX ← ECX 1;
 - if ECX > 0 and ZF=0, jump to destination
- Useful when scanning an array for the first element that matches a given value.

LOOPNZ Example

The following code finds the first positive value in an array:

```
.data
array SWORD -3,-6,-1,-10,10,30,40,4
sentinel SWORD 0
.code
   mov esi, OFFSET array
   mov ecx, LENGTHOF array
next:
   test WORD PTR [esi],8000h ; test sign bit
   pushfd
                               ; push flags on stack
   add esi, TYPE array
   popfd
                               ; pop flags from stack
   loopnz next
                               ; continue loop
   jnz quit
                               ; none found
   sub esi, TYPE array
                               ; ESI points to value
quit:
```

What's Next

- Boolean and Comparison Instructions
- Conditional Jumps
- Conditional Loop Instructions
- Conditional Structures
- Application: Finite-State Machines
- Conditional Control Flow Directives

Conditional Structures

- Block-Structured IF Statements
- Compound Expressions with AND
- Compound Expressions with OR
- WHILE Loops

Block-Structured IF Statements

Assembly language programmers can easily translate logical statements written in C++/Java into assembly language. For example:

```
if( op1 == op2 )
    X = 1;
else
    X = 2;
```

```
mov eax,op1
  cmp eax,op2
  jne L1
  mov X,1
  jmp L2
L1: mov X,2
L2:
```

Compound Expression with AND (1 of 3)

- When implementing the logical AND operator, consider that HLLs use short-circuit evaluation
- In the following example, if the first expression is false, the second expression is skipped:

```
if (al > bl) AND (bl > cl)
X = 1;
```

Compound Expression with AND (2 of 3)

```
if (al > bl) AND (bl > cl)
X = 1;
```

This is one possible implementation . . .

Compound Expression with AND (3 of 3)

```
if (al > bl) AND (bl > cl)
X = 1;
```

But the following implementation uses 29% less code by reversing the first relational operator. We allow the program to "fall through" to the second expression:

What's Next

- Boolean and Comparison Instructions
- Conditional Jumps
- Conditional Loop Instructions
- Conditional Structures
- Application: Finite-State Machines
 - Reading material
- Conditional Control Flow Directives

What's Next

- Boolean and Comparison Instructions
- Conditional Jumps
- Conditional Loop Instructions
- Conditional Structures
- Application: Finite-State Machines
- Conditional Control Flow Directives

Creating IF Statements

- Runtime Expressions
- Relational and Logical Operators
- MASM-Generated Code
- .REPEAT Directive
- .WHILE Directive

Runtime Expressions

- IF, .ELSE, .ELSEIF, and .ENDIF can be used to evaluate runtime expressions and create block-structured IF statements.
- Examples:

```
.IF eax > ebx
    mov edx,1
.ELSE
    mov edx,2
.ENDIF
```

```
.IF eax > ebx && eax > ecx
    mov edx,1
.ELSE
    mov edx,2
.ENDIF
```

 MASM generates "hidden" code for you, consisting of code labels, CMP and conditional jump instructions.

Relational and Logical Operators

Operator	Description
expr1 == expr2	Returns true when expression1 is equal to expr2.
expr1 != expr2	Returns true when expr1 is not equal to expr2.
expr1 > expr2	Returns true when expr1 is greater than expr2.
expr1 >= expr2	Returns true when <i>expr1</i> is greater than or equal to <i>expr2</i> .
expr1 < expr2	Returns true when expr1 is less than expr2.
expr1 <= expr2	Returns true when expr1 is less than or equal to expr2.
! expr	Returns true when expr is false.
expr1 && expr2	Performs logical AND between expr1 and expr2.
expr1 expr2	Performs logical OR between expr1 and expr2.
expr1 & expr2	Performs bitwise AND between expr1 and expr2.
CARRY?	Returns true if the Carry flag is set.
OVERFLOW?	Returns true if the Overflow flag is set.
PARITY?	Returns true if the Parity flag is set.
SIGN?	Returns true if the Sign flag is set.
ZERO?	Returns true if the Zero flag is set.

```
.data
val1   DWORD 5
result DWORD ?

.code
    mov eax,6
mov eax,6
cmp eax,val1
jbe @C0001
mov result,1
.ENDIF

.code
    mov eax,6
cmp eax,val1
jbe @C0001
mov result,1
@C0001:
```

MASM automatically generates an unsigned jump (JBE) because val1 is unsigned.



```
.data
val1    SDWORD 5
result SDWORD ?
.code
    mov eax, 6
mov eax, 6
cmp eax, val1
jle @C0001
mov result, 1
ec0001:
```

MASM automatically generates a signed jump (JLE) because val1 is signed.

```
.data
result DWORD ?

.code
mov ebx,5
mov eax,6
mov eax,6
.IF eax > ebx
mov result,1
.ENDIF
Generated code:

mov ebx,5
mov eax,6
cmp eax,ebx
jbe @C0001
mov result,1
@C0001:
```

MASM automatically generates an unsigned jump (JBE) when both operands are registers . . .

```
.data
result SDWORD ?

.code

mov ebx,5
mov eax,6

mov eax,6

.IF SDWORD PTR eax > ebx
mov result,1
.ENDIF
Generated code:

mov ebx,5
mov eax,6
cmp eax,ebx
jle @C0001
mov result,1
@C0001:
```

. . . unless you prefix one of the register operands with the SDWORD PTR operator. Then a signed jump is generated.

.REPEAT Directive

Executes the loop body before testing the loop condition associated with the .UNTIL directive.

Example:

```
; Display integers 1 - 10:

mov eax,0
.REPEAT
  inc eax
  call WriteDec
  call Crlf
.UNTIL eax == 10
```

.WHILE Directive

Tests the loop condition before executing the loop body The .ENDW directive marks the end of the loop.

Example:

```
; Display integers 1 - 10:

mov eax,0
.WHILE eax < 10
  inc eax
  call WriteDec
  call Crlf
.ENDW</pre>
```

CHAPTER 7: INTEGER ARITHMETIC

Chapter Overview


- Shift and Rotate Instructions
- Shift and Rotate Applications
- Multiplication and Division Instructions
- Extended Addition and Subtraction
- ASCII and Unpacked Decimal Arithmetic
- Packed Decimal Arithmetic

7.1 Shift and Rotate Instructions

- Logical vs Arithmetic Shifts
- SHL Instruction
- SHR Instruction
- SAL and SAR Instructions
- ROL Instruction
- ROR Instruction
- RCL and RCR Instructions
- SHLD/SHRD Instructions


Logical Shift

 A logical shift fills the newly created bit position with zero:



Arithmetic Shift

 An arithmetic shift fills the newly created bit position with a copy of the number's sign bit:



SHL Instruction

 The SHL (shift left) instruction performs a logical left shift on the destination operand, filling the lowest bit with 0.

 $(cf) \longleftarrow 1 \quad 1 \quad 0 \quad 0 \quad 1 \quad 1 \quad 1 \quad 1$ $1 \quad 0 \quad 0 \quad 1 \quad 1 \quad 1 \quad 1 \quad 0 \longleftarrow$

Operand types for SHL:

SHL reg,imm8
SHL mem,imm8
SHL reg,CL
SHL mem,CL

(Same for all shift and rotate instructions)

Fast Multiplication

Shifting left 1 bit multiplies a number by 2


Shifting left n bits multiplies the operand by 2^n

For example, $5 * 2^2 = 20$

```
mov d1,5
shl d1,2 ; DL = 20
```

SHR Instruction

 The SHR (shift right) instruction performs a logical right shift on the destination operand. The highest bit position is filled with a zero.




Shifting right n bits divides the operand by 2^n

```
mov d1,80
shr d1,1 ; DL = 40
shr d1,2 ; DL = 10
```

SAL and SAR Instructions

- SAL (shift arithmetic left) is identical to SHL.
- SAR (shift arithmetic right) performs a right arithmetic shift on the destination operand.



An arithmetic shift preserves the number's sign.


```
mov dl,-80

sar dl,1 ; DL = -40

sar dl,2 ; DL = -10
```

ROL Instruction


- ROL (rotate) shifts each bit to the left
- The highest bit is copied into both the Carry flag and into the lowest bit
- No bits are lost



```
mov al,11110000b
rol al,1 ; AL = 11100001b
mov dl,3Fh
rol dl,4 ; DL = F3h
```

ROR Instruction


- ROR (rotate right) shifts each bit to the right
- The lowest bit is copied into both the Carry flag and into the highest bit
- No bits are lost



```
mov al,11110000b
ror al,1 ; AL = 01111000b
mov dl,3Fh
ror dl,4 ; DL = F3h
```

RCL Instruction

- RCL (rotate carry left) shifts each bit to the left
- Copies the most significant bit to the Carry flag
- Copies the Carry flag to the least significant bit



```
clc ; CF = 0


mov bl,88h ; CF,BL = 0 10001000b

rcl bl,1 ; CF,BL = 1 00010000b

rcl bl,1 ; CF,BL = 0 00100001b
```

RCR Instruction

- RCR (rotate carry right) shifts each bit to the right
- Copies the least significant bit to the Carry flag
- Copies the Carry flag to the most significant bit



SHLD Instruction (Shift Left Double)

- Shifts a destination operand a given number of bits to the left
- The bit positions opened up by the shift are filled by the most significant bits of the source operand
- The source operand is not affected
- Syntax:

SHLD destination, source, count


Operand types:

```
SHLD reg16/32, reg16/32, imm8/CL
SHLD mem16/32, reg16/32, imm8/CL
```

SHLD Example

Shift count of 1:


```
mov al,11100000b
mov bl,10011101b
shld al,bl,1
```



Another SHLD Example

Shift wval 4 bits to the left and replace its lowest 4 bits with the high 4 bits of AX:

.data
wval WORD 9BA6h
.code
mov ax,0AC36h
shld wval,ax,4



SHRD Instruction

- Shifts a destination operand a given number of bits to the right
- The bit positions opened up by the shift are filled by the least significant bits of the source operand
- The source operand is not affected
- Syntax:

SHRD destination, source, count


Operand types:

```
SHRD reg16/32, reg16/32, imm8/CL
SHRD mem16/32, reg16/32, imm8/CL
```

SHRD Example

Shift count of 1:

```
mov al,11000001b
mov bl,00011101b
shrd al,bl,1
```



Another SHRD Example

Shift AX 4 bits to the right and replace its highest 4 bits with the low 4 bits of DX:

mov ax,234Bh mov dx,7654h shrd ax,dx,4

DX AX
7654 234B

After: 7654 4234

What's Next

- Shift and Rotate Instructions
- Shift and Rotate Applications
- Multiplication and Division Instructions
- Extended Addition and Subtraction
- ASCII and Unpacked Decimal Arithmetic
- Packed Decimal Arithmetic

7.2 Multiplication and Division Instructions

- MUL Instruction
- IMUL Instruction
- DIV Instruction
- Signed Integer Division
- CBW, CWD, CDQ Instructions
- IDIV Instruction
- Implementing Arithmetic Expressions

MUL Instruction

- In 32-bit mode, MUL (unsigned multiply) instruction multiplies an 8-, 16-, or 32-bit operand by either AL, AX, or EAX.
- The instruction formats are:

```
MUL r/m8
```

MUL r/m16

MUL r/m32

Implied operands:

Multiplicand	Multiplier	Product
AL	r/m8	AX
AX	r/m16	DX:AX
EAX	r/m32	EDX:EAX

64-Bit MUL Instruction

- In 64-bit mode, MUL (unsigned multiply) instruction multiplies a 64-bit operand by RAX, producing a 128-bit product.
- The instruction formats are:

```
MUL r/m64
```

Example:

Summary (Chap 5)

- Use the Irvine32 library for all standard I/O and data conversion
 - Want to learn more? Study the library source code

Summary (Chap 6)

- Bitwise instructions (AND, OR, XOR, NOT, TEST)
 - manipulate individual bits in operands
- CMP compares operands using implied subtraction
 - sets condition flags
- Conditional Jumps & Loops
 - equality: JE, JNE
 - flag values: JC, JZ, JNC, JP, ...
 - signed: JG, JL, JNG, ...
 - unsigned: JA, JB, JNA, ...
 - LOOPZ, LOOPNZ, LOOPE, LOOPNE
- Flowcharts logic diagramming tool

Summary (Chap 7)

- Shift and rotate instructions are some of the best tools of assembly language
 - finer control than in high-level languages
 - SHL, SHR, SAR, ROL, ROR, RCL, RCR
- MUL integer operations
 - close relatives of SHL

Homework

- Reading Chap 5 -- 7
- Exercises

Thanks!