Jobs/Apps/Systems Parameter Matrix (export version)

Cloud and Interactive Computing

Exported on 05/03/2021

Table of Contents

1	Common attributes for Jobs, Applications and Systems	.3
2	Directory Semantics	.6
	. System Directories	

1 Common attributes for Jobs, Applications and Systems

Attribute	J o b	A p p	S y s	Notes
System Definition Values [§]				
host			х	the host associated with this system
canExec			х	boolean flag indicating if system can be used to execute jobs.
jobWorkingDir			х	See Directory Semantics; TACC systems will often assign HOST_EVAL(\$SCRATCH)
jobExecClass			х	One of: NORMAL, PROTECTED
jobContainerRunt imes			х	Zero or more: Docker, Singularity, etc.
jobEnvVariables	х	х	х	environment variables passed into application containers
jobMaxJobs		х	х	Apps can lower the limit set by Systems
jobMaxJobsPerUs er		х	х	Apps can lower the limit set by Systems
joblsBatch			Х	boolean flag indicating if system uses a batch scheduler to run jobs. By default this is <i>false</i> .
batchScheduler			х	slurm, pbs, condor, etc.
batchLogicalQue ues			х	Tapis-defined queues
batchDefaultLogi calQueue			х	Default tapis-defined queue
batchHPCQueue			х	Name of actual queue on HPC system
jobCapabilities			х	parameters.execSystemConstraints field in SubmitJobRequest
dtnSystemId			х	An alternate system to use as a Data Transfer Node (DTN).
dtnMountPoint			х	mount point on the execution system (maps dtnMountSourcePath from DTN system)

Attribute	J o b	A p p	S y s	Notes
dtnMountSource Path			х	the relative path that defines the DTN source directory relative to the DTN rootDir.
isDtn			х	boolean flag indicating if system will be used as a DTN.
Job Request Values [§]				
job name	Х			User supplied job name
job description	х	х		Long description
archiveOnAppErr or	х	х		default = true
dynamicExecSyst em	х	х		default = false, use constraints to dynamically choose a best fit execution system
execSystemId	х	х		required
execSystemExecD ir	х	х		See Directory Semantics
execSystemInput Dir	х	х		See Directory Semantics
execSystemOutp utDir	х	х		See Directory Semantics
execSystemLogic alQueue	х	х	*	Defaults to system's batchDefaultLogicalQueue
archiveSystemId	х	х		Set to enable archiving; archiveSystemDir must also be set.
archiveSystemDir	х	х		See Directory Semantics
nodeCount	х	х		
coresPerNode	х	х		
memoryMB	х	х		
maxMinutes	х	х		

Attribute	J o b	A p p	S y s	Notes
fileInputs	х	х		See SubmitJobRequest
parameterSet	х	х		See SubmitJobRequest
execSystemConst raints	х	х		See SubmitJobRequest, (array of sql strings)
subscriptions	х	х		See SubmitJobRequest (array of notification subscriptions)
tags	х	х		list of strings

[§] All App fields that can be overridden in a Job request are embedded in a jobAttributes object in App's JSON schema.

2 Directory Semantics

2.1 System Directories

The <u>required</u> jobWorkingDir value in a system definition specifies the root directory where most I/O occurs during job execution. The following syntax can be used:

- 1. **/{path}** the path relative to *rootDir* in the System definition. An empty {path} designates the system's *rootDir* itself. Macro substitution is applied to calculate the path.
- 2. **HOST_EVAL(\$SOME_ENV_VARIABLE)** the value of the specified environment variable when evaluated on the host under the job's effective user ID. This is a dynamic value determined at job submission time. This function extracts specific environment variable values for use during job setup. In particular, the TACC-specific values of \$HOME, \$WORK, \$SCRATCH and \$FLASH can be referenced.

The specified environment variable name is used *as-is:* it is <u>not</u> subject to macro substitution. However, the function call can have a path string appended to it, such as in HOST_EVAL(\$SCRATCH)/my/dir, and macro substitution is applied to the path string.