

CacaoSoundCues Manual

A sound cue player for the stage

Version β2.9.0 / October 2026

What this manual covers

1. What CacaoSoundCues does
2. Installing and the main screen
3. Assigning sound effects to keys
4. “Lists” that play music in order, e.g. intermission music
5. Running the show (Show Mode and keys)
6. Settings and troubleshooting

> Requires **macOS 14 or later**. No internet connection needed. A MacBook alone is enough to run sound cues for a show.

What CacaoSoundCues does

Play from keys (sound cues)

- Assign audio files to **keys on the keyboard** — press to play instantly
- Set the play range, fade in/out and repeat for each sound
- Press again to fade out and stop

Play lists in order

- Play intermission music and more **in a set order**
- Choose “after the previous track”, “overlap (crossfade)” or “on Return”
- Plays together with key sound effects

> Sounds are loaded in advance, so there is almost no delay between pressing a key and hearing it.

1. Installing and launching

1. Double-click **CacaoSoundCues-2.9.0.dmg**
2. Drag **CacaoSoundCues** onto **Applications**
3. Close the dmg (eject the disk icon on the desktop)
4. Double-click CacaoSoundCues in the Applications folder

Supported audio: wav / aiff / mp3 / m4a and anything else your Mac can play. On launch, the cue sheet you used last opens automatically.




If a warning such as “cannot be verified” appears

macOS 15 or later: close it, then click **“Open Anyway”** in **System Settings › Privacy & Security**.


macOS 14: **right-click** the app → **Open** → **Open**. After the first time, it opens normally.

2. The main screen



Top: buttons, master volume / Middle: keyboard / Bottom left: list / Bottom right: selected sound

3. Cue sheets (the files you save)



- Everything for one show is saved as a **cue sheet (.ccsc)**
- **The audio files are copied into the cue sheet**
- Carry the cue sheet on a USB stick and it works **as is on another Mac**

Action	Menu
New	File › New Cue Sheet ⌘ N
Open	File › Open… ⌘ O
Save	File › Save ⌘ S

4. Assigning sounds to keys

1. **Drag** an audio file from the Finder **onto a key** on screen
2. The key gets a color and a name — done
3. Press the key to play. **Press again to stop**

Changing assignments

- **Drag** an assigned key **onto another key** to move it
- If the other key is assigned too, they **swap**
- To remove: right-click the key → “Remove assignment”

Keys you can use


Number, letter and symbol keys. **F1–F12** and the **numeric keypad** can be turned on too (the ≡ button in the top bar).

Reserved keys (controls)

Key	Role
return	Next track in the list
space	End the current list track
esc	Stop everything

5. Sound settings (click a key to show them on the right)

Item	What it does
Name and color	Shown on the key
When pressed again	Stop / restart / layer / nothing
Play range	The part to play (start and end)
Fade in / out	In seconds. **0 s = cut**
Curve	Linear / Equal power / S-curve / Custom
Repeat	Until stopped, or a set count
Volume	In dB. “0dB” resets it



Use “Preview” to listen.

6. Range and fades on the waveform

Drag	To change
Green line	Where playback starts
Red line	Where playback ends
Orange dots on the top edge	Fade lengths
White squares	Fade shape (Bézier curve)

- Moving a white square switches the curve to “Custom”
- The **dotted line** is the fade-out used when you stop the sound
- During playback, click the waveform to jump there


While playing

During a fade, a yellow line and dot move along the fade shape.

- Fade in: the dot rises ↑
- Fade out: the dot falls ↓

> You can also type fade times in the fields below. Press `return` to confirm.

7. Making a list (e.g. intermission music)



Click ＋ next to “List”, then drag track files into the list. You can also set a start/stop key (e.g. M).

8. When each track starts

Click a track to choose on the right.

Timing	Behavior
On Return	No auto-play. Plays when you press `return`. Can also wait n seconds after Return
When the previous track ends	Plays automatically after the previous track. You can set a gap
Overlap the previous track	Starts over the end of the previous track (**crossfade**). The previous one fades out automatically

- Check “Loop to the top at the end” to play the list over and over
- **Only one list plays at a time**. Starting another list stops the current one

9. List controls

Key	Action
return	**Next track**. The current track stops with its own fade-out. Starts the list if it is stopped
return twice	Skip the “wait n seconds” and play at once
space	**End the current track early**. The next one follows its own timing
↑ ↓ / double-click	**Choose the next track** (does not play). It is marked “Next”
Start/stop key	Start / stop that list
esc	**Fade out everything**. Press again to cut


> Example: when the curtain falls, press space to end the music → after the blackout, press return for the next track.

10. Hiding the keyboard (key list)


Click **“Keyboard”** in the top bar to hide the keyboard and show **only the assigned keys** as a list.

- Organize keys into **groups** (e.g. Act 1, Act 2)
- Drag rows to reorder
- Right-click → “Move to group”
- Drag an audio file onto the list → press the key to assign

For list-centered shows, this view is easier to read.



11. Show Mode



“Show Mode” (⇧ ⌘ L) turns the top bar red and shows the current track, time left and next track in large type.

11. What works in Show Mode

Works

- Playing and stopping keys
- return space ↑ ↓ esc
- Double-click to choose the next track
- Master volume
- Save

Locked (to prevent accidents)

- Changing sound settings or assignments
- Editing lists and groups
- Preview (the audience would hear it)
- Jumping by clicking the waveform
- New / Open

> Leaving Show Mode and quitting the app both ask for confirmation. Show Mode stays on after a restart.

12. Settings (CacaoSoundCues › Settings… ⌘ ,)


Language

Switch between 日本語 and English. The menu bar changes after a restart.

For other languages, export the translation template (English), translate it, and put it in the language folder.

Initial settings for new sounds

The starting fades and timing used when you add sounds to keys or lists.



13. Checklist before the show

- □ The cue sheet is **saved** (the title does not say “Unsaved”)
- □ Every sound was played on **the Mac and speakers used in the show**
- □ Master volume and the Mac’s volume are set
- □ **The first track of the list is marked “Next”**
- □ Notifications are off (Focus mode). The app prevents sleep itself
- □ **Show Mode** is on
- □ You know where `esc` (stop everything) is

> Keep a **backup** of the cue sheet on a USB stick too.

14. Troubleshooting

Problem	What to do
A key does not play	A text field still has the cursor. **Click the list or a key**, or press return
F keys do not play	Hold fn, or turn on “Use F1, F2, etc. keys as standard function keys” in macOS
A key shows ⚠	The audio file is missing or unreadable. Assign it again
Too quiet / no sound	Check master volume, the sound’s volume, and the output device (top right)
Cannot edit in Show Mode	Click “Show Mode On” in the top bar to leave it
Played the wrong sound	Press that key again. For everything, esc

Key reference

Key	Action
Assigned key	Play / press again to stop
return	Next track in the list (twice: skip the wait)
space	End the current list track
↑ ↓	Choose the next list track
esc	Fade out everything (twice: cut)
⇧ ⌘ L	Show Mode on / off
⌘ S / ⌘ O / ⌘ N	Save / Open / New
⌘ ,	Settings