String conversion and formatting

```
System Message: ERROR/3 (p:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main][Doc][c-api]conversion.rst, line 1)

Unknown directive type "highlight".

.. highlight:: c
```

Functions for number conversion and formatted string output.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main][Doc][c-api]conversion.rst, line 11)

Unknown directive type "c:function".

.. c:function:: int PyOS_snprintf(char *str, size_t size, const char *format, ...)

Output not more than *size* bytes to *str* according to the format string *format* and the extra arguments. See the Unix man page :manpage:`snprintf(3)`.
```

 $System\,Message:\,ERROR/3\, (\mbox{D:\noboarding-resources}\xspaces) ample-onboarding-resources\xspaces$

Unknown directive type "c:function".

```
.. c:function:: int PyOS_vsnprintf(char *str, size_t size, const char *format, va_list va)

Output not more than *size* bytes to *str* according to the format string
*format* and the variable argument list *va*. Unix man page
:manpage:`vsnprintf(3)`.
```

ccfunc: 'PyOS_snprintf' and ccfunc: 'PyOS_vsnprintf' wrap the Standard C library functions ccfunc: 'snprintf' and ccfunc: 'vsnprintf'. Their purpose is to guarantee consistent behavior in corner cases, which the Standard C functions do not.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] conversion.rst, line 23); backlink

Unknown interpreted text role "c:func".

 $System\,Message: ERROR/3 \ (\cite{D:Conboarding-resources}) sample-onboarding-resources \cite{Conboarding-resources}) in the conboarding-resources \cite{Conboarding-resources} in the conboa$

Unknown interpreted text role "c:func".

Unknown interpreted text role "c:func".

 $System\ Message:\ ERROR/3\ (D:\ londoarding-resources\ sample-onboarding-resources\ londoarding-resources\ londo$

Unknown interpreted text role "c:func".

The wrappers ensure that str[size-1] is always '\0' upon return. They never write more than size bytes (including the trailing '\0') into str. Both functions require that str != NULL, size > 0, format != NULL and size < INT_MAX.

The return value (rv) for these functions should be interpreted as follows:

- When 0 <= rv < size, the output conversion was successful and rv characters were written to str (excluding the trailing '\0' byte at str[rv]).
- When rv >= size, the output conversion was truncated and a buffer with rv + 1 bytes would have been needed to succeed. str[size-1] is '\0' in this case.
- When rv < 0, "something bad happened." str[size-1] is '\0' in this case too, but the rest of str is undefined. The exact cause of the error depends on the underlying platform

The following functions provide locale-independent string to number conversions.

 $System\ Message:\ ERROR/3\ (\texttt{D:\onboarding-resources}\ sample-onboarding-resources\ cpython-main\ [\texttt{Doc}]\ [\texttt{c-api}]\ conversion.rst,\ line\ 50)$

Unknown directive type "c:function".

```
Convert a string ``s`` to a :c:type:`double`, raising a Python
        exception on failure. The set of accepted strings corresponds to
        the set of strings accepted by Python's :func:`float` constructor,
        except that ``s`` must not have leading or trailing whitespace.
        The conversion is independent of the current locale.
       If ``endptr`` is ``NULL``, convert the whole string. Raise :exc:`ValueError` and return ``-1.0`` if the string is not a valid
        representation of a floating-point number.
       If endptr is not ``NULL``, convert as much of the string as possible and set ``*endptr`` to point to the first unconverted
       character. If no initial segment of the string is the valid representation of a floating-point number, set ``*endptr`` to point
        to the beginning of the string, raise ValueError, and return
         ``-1.0``
       If ``s`` represents a value that is too large to store in a float
        (for example, ``"le500"`` is such a string on many platforms) then if ``overflow_exception`` is ``NULL`` return ``Py_HUGE_VAL`` (with
       an appropriate sign) and don't set any exception. Otherwise, ``overflow_exception`` must point to a Python exception object; raise that exception and return ``-1.0``. In both cases, set ``*endptr`` to point to the first character after the converted value.
       If any other error occurs during the conversion (for example an
       out-of-memory error), set the appropriate Python exception and return ``-1.0``.
        .. versionadded:: 3.1
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-
main\Doc\c-api\[cpython-main][Doc][c-api]conversion.rst, line 84)
Unknown directive type "c:function".
    .. c:function:: char* PyOS double to string(double val, char format code, int precision, int flags, int
        Convert a :c:type:`double` *val* to a string using supplied
        *format code*, *precision*, and *flags*.
       *format_code* must be one of ``'e'``, ``'E'``, ``'f'``, ``'F'``, ``'g'``, ``'G'`` or ``'r'``. For ``'r'``, the supplied *precision* must be 0 and is ignored. The ``'r'`` format code specifies the
       standard :func: `repr` format.
        \mbox{\ ^{``Py\_DTSF\_SIGN``}} means to always precede the returned string with a sign
         character, even if *val* is non-negative.
        * ``Py_DTSF_ADD_DOT_0`` means to ensure that the returned string will not look
         like an integer.
        \star ``Py_DTSF_ALT`` means to apply "alternate" formatting rules. See the
          documentation for the :c:func:`PyOS_snprintf` ``'#'`` specifier for
          details.
       If *ptype* is non-``NULL``, then the value it points to will be set to one of ``Py_DTST_FINITE``, ``Py_DTST_INFINITE``, or ``Py_DTST_NAN``, signifying that
        *val* is a finite number, an infinite number, or not a number, respectively.
        The return value is a pointer to *buffer* with the converted string or
         `NULL`` if the conversion failed. The caller is responsible for freeing the
        returned string by calling :c:func:`PyMem_Free`.
        .. versionadded:: 3.1
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-
main\Doc\c-api\[cpython-main][Doc][c-api]conversion.rst, line 118)
Unknown directive type "c:function".
    .. c:function:: int PyOS_stricmp(const char *s1, const char *s2)
```

.. c:function:: double PyOS_string_to_double(const char *s, char **endptr, PyObject *overflow exception)

.. c:runction:: int PyOS_stricmp(const cnar *s1, const cnar *s2)

Case insensitive comparison of strings. The function works almost identically to :c:func:`strcmp` except that it ignores the case.

$\verb|main\Doc\c-api\[cpython-main][Doc][c-api]]| conversion.rst, line 124)$

Unknown directive type "c:function".

.. c:function:: int PyOS_strnicmp(const char *s1, const char *s2, Py_ssize_t size)

Case insensitive comparison of strings. The function works almost identically to :c:func:`strncmp` except that it ignores the case.