Call Protocol

```
System Message: ERROR/3 (p:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main][Doc][c-api]call.rst, line 1)

Unknown directive type "highlight".

.. highlight:: c
```

CPython supports two different calling protocols: tp_call and vectorcall.

The tp call Protocol

Instances of classes that set :c:member: `~PyTypeObject.tp_call` are callable. The signature of the slot is:

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] call.rst, line 14); backlink
Unknown interpreted text role "cmember".

```
PyObject *tp_call(PyObject *callable, PyObject *args, PyObject *kwargs);
```

A call is made using a tuple for the positional arguments and a dict for the keyword arguments, similarly to callable (*args, **kwargs) in Python code. args must be non-NULL (use an empty tuple if there are no arguments) but kwargs may be NULL if there are no keyword arguments.

This convention is not only used by tp_call : c:member:'~PyTypeObject.tp_new' and :c:member:'~PyTypeObject.tp_init' also pass arguments this way.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main][Doc][c-api]call.rst, line 25); backlink

Unknown interpreted text role "c:member".
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] call.rst, line 25); backlink
Unknown interpreted text role "c:member".

To call an object, use :c:finc:'PyObject_Call' or another :ref.'call API <capi-call>'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] call.rst, line 29); backlink
Unknown interpreted text role "c:fine".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] call.rst, line 29); backlink
Unknown interpreted text role "ref".

The Vectorcall Protocol

```
System Message: ERROR/3 (p:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main][Doc][c-api]call.rst, line 38)

Unknown directive type "versionadded".

.. versionadded:: 3.9
```

The vectorcall protocol was introduced in PEP 590 as an additional protocol for making calls more efficient.

As rule of thumb, CPython will prefer the vectorcall for internal calls if the callable supports it. However, this is not a hard rule. Additionally, some third-party extensions use tp_call directly (rather than using :c:func: PyObject_Call'). Therefore, a class supporting vectorcall must also implement :c:member: ~PyTypeObject.tp_call'. Moreover, the callable must behave the same regardless of which protocol is used. The recommended way to achieve this is by setting :c:member: ~PyTypeObject.tp_call' to :c:func: PyVectorcall_Call'. This bears repeating:

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] call.rst, line 43); backlink
Unknown interpreted text role "c:fine".
```

 $System \, Message: ERROR/3 \, (\texttt{D:\onboarding-resources} \times \texttt{sample-onboarding-resources} \times \texttt{cpython-main} \, \texttt{Doc} \, \texttt{[c-api]} \, \texttt{call.rst}, \, \textbf{line 43}); \, \textbf{\textit{backlink}}$

Unknown interpreted text role "c:member".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] call.rst, line 43); backlink

Unknown interpreted text role "c:member".

 $System\,Message:\,ERROR/3\,(\texttt{D:}\nonlineseques) sample-onboarding-resources \verb|\continuous ample-onboarding-resources| sample-onboarding-resources| sample-onboard$ main\Doc\c-api\[cpython-main][Doc][c-api]call.rst, line 43); backlink

Unknown interpreted text role "c:func".

Warning

A class supporting vectorcall must also implement :c:member: `~PyTypeObject.tp_call` with the same semantics.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboardingresources\cpython-main\Doc\c-api\[cpython-main][Doc][c-api]call.rst, line 57); backlink

Unknown interpreted text role "c:member".

A class should not implement vectorcall if that would be slower than tp_call . For example, if the callee needs to convert the arguments to an args tuple and kwargs dict anyway, then there is no point in implementing vectorcall.

Classes can implement the vectorcall protocol by enabling the const. Py_TPFLAGS_HAVE_VECTORCALL flag and setting .cmember.`~PyTypeObject.tp vectorcall offset` to the offset inside the object structure where a vectorcallfunc appears. This is a pointer to a function with the following signature:

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpythonmain\Doc\c-api\[cpython-main][Doc][c-api]call.rst, line 65); backlink

Unknown interpreted text role "const".

 $System\,Message: ERROR/3\,(\texttt{D:\nboarding-resources}) sample-onboarding-resources \verb|\color= color= c$ main\Doc\c-api\[cpython-main][Doc][c-api]call.rst, line 65); backlink

Unknown interpreted text role "c:member".

System Message: ERROR/3 (D:\onboarding-resources\sa ple-onboarding-resources\cpvthonmain\Doc\c-api\[cpython-main][Doc][c-api]call.rst, line 71)

Unknown directive type "c:type".

```
.. c:type:: PyObject *(*vectorcallfunc)(PyObject *callable, PyObject *const *args, size_t nargsf, PyObject *kwn
```

- callable is the object being called.
- args is a C array consisting of the positional arguments followed by the values of the keyword arguments. This can be NULL if there are no arguments.
- nargsf is the number of positional arguments plus possibly the

:const: PY_VECTORCALL_ARGUMENTS_OFFSET flag. To get the actual number of positional arguments from nargsf, use :c:func:`PyVectorcall_NARGS`.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboardingces\cpython-main\Doc\c-api\[cpython-main][Doc][c-api]call.rst, line 78); backlink

Unknown interpreted text role "const".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboardingresources\cpython-main\Doc\c-api\[cpython-main][Doc][c-api]call.rst, line 78); backlink

Unknown interpreted text role "c:func".

• kwnames is a tuple containing the names of the keyword arguments;

in other words, the keys of the kwargs dict. These names must be strings (instances of str or a subclass) and they must be unique. If there are no keyword arguments, then kwnames can instead be NULL.

main\Doc\c-api\[cpython-main][Doc][c-api]call.rst, line 87)

Unknown directive type "c:macro".

```
.. c:macro:: PY VECTORCALL ARGUMENTS OFFSET
   If this flag is set in a vectorcall *nargsf* argument, the callee is allowed to temporarily change ``args[-1]``. In other words, *args* points to
  argument 1 (not 0) in the allocated vector.

The callee must restore the value of ``args[-1]`` before returning.
   For :c:func: PyObject_VectorcallMethod`, this flag means instead that
    ``args[0]`` may be changed.
   Whenever they can do so cheaply (without additional allocation), callers
   are encouraged to use :const: PY_VECTORCALL_ARGUMENTS_OFFSET
   Doing so will allow callables such as bound methods to make their onward
   calls (which include a prepended *self* argument) very efficiently.
```

To call an object that implements vectorcall, use a ref:call API <capi-call>` function as with any other callable.
refine:
PyObject Vectorcall
will usually be most efficient.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] call.rst, line 102); backlink

Unknown interpreted text role 'ref'.

Unknown interpreted text role "c:func".

Note

In CPython 3.8, the vectorcall API and related functions were available provisionally under names with a leading underscore: _PyObject_Vectorcall, _Py_TPFLAGS_HAVE_VECTORCALL, _PyObject_VectorcallMethod, _PyVectorcall_Function, _PyObject_CallOneArg, _PyObject_CallMethodNoArgs, _PyObject_CallMethodOneArg. Additionally, PyObject_VectorcallDict was available as _PyObject FastCallDict. The old names are still defined as aliases of the new, non-underscored names.

Recursion Control

When using tp_call , callees do not need to worry about recursion: CPython uses c:finnc: Py_EnterRecursiveCall and recursiveCall for calls made using tp_call.

 $System\ Message: ERROR/3\ (D:\onboarding-resources\sample-onboarding-resources\cpython-main\coc-api\cpython-main\coc-api\cpython-main\coc-api\coc-ap$

Unknown interpreted text role "ref".

 $System\ Message: ERROR/3\ (p:\onboarding-resources\ sample-onboarding-resources\ cpython-main\ Doc\ c-api\ [cpython-main\]\ [Doc\]\ [c-api\]\ call.rst,\ line\ 123);\ backlink$

Unknown interpreted text role "c:func".

 $System\ Message: ERROR/3\ (D:\noboarding-resources\sumple-onboarding-resources\cpython-main\cp$

Unknown interpreted text role "c:func".

For efficiency, this is not the case for calls done using vectorcall: the callee should use *Py_EnterRecursiveCall* and *Py_LeaveRecursiveCall* if needed.

Vectorcall Support API

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] call.rst, line 136)

Unknown directive type "c:function".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] call.rst, line 151)

Unknown directive type "c:function".

```
.. c:function:: vectorcallfunc PyVectorcall_Function(PyObject *op)

If *op* does not support the vectorcall protocol (either because the type does not or because the specific instance does not), return *NULL*.

Otherwise, return the vectorcall function pointer stored in *op*.

This function never raises an exception.

This is mostly useful to check whether or not *op* supports vectorcall, which can be done by checking ``PyVectorcall_Function(op) != NULL``.

This function is not part of the :ref:`limited API <stable>`.

.. versionadded:: 3.8
```

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main][Doc][c-api]call.rst, line 165)

Unknown directive type "c:function".

.. c:function:: PyObject* PyVectorcall_Call(PyObject *callable, PyObject *tuple, PyObject *dict)

Call *callable*'s :c:type:`vectorcallfunc` with positional and keyword arguments given in a tuple and dict, respectively.

This is a specialized function, intended to be put in the :c:member:`~PyTypeObject.tp_call` slot or be used in an implementation of ``tp_call` It does not check the :const:`Py_TPFLAGS_HAVE_VECTORCALL` flag and it does not fall back to ``tp_call``.

This function is not part of the :ref:`limited API <stable>`.

.. versionadded:: 3.8
```

Object Calling API

Various functions are available for calling a Python object. Each converts its arguments to a convention supported by the called object $\hat{a} \in \mathcal{C}$ either tp_call or vectorcall. In order to do as little conversion as possible, pick one that best fits the format of data you have available.

The following table summarizes the available functions; please see individual documentation for details.

Function	callable	args	kwargs
:c:func:`PyObject_Call`			
System Message: ERROR/3 (D:\onboarding- resources\sample-onboarding- resources\cpython-main\Doc\c- api\[cpython-main] [Doc] [c- api] call.rst, line 198); backlink Unknown interpreted text role "c:fimc".	PyObject *	tuple	dict/null
ccfinc: `PyObject_CallNoArgs`			
System Message: ERROR/3 (D:\onboarding- resources\sample-onboarding- resources\cpython-main\Doc\c- api\[cpython-main] [Doc] [c- api]call.rst, line 200); backlink Unknown interpreted text role "c:fimc".	PyObject *		
c:func:`PyObject_CallOneArg`			
System Message: ERROR/3 (D:\onboarding- resources\sample-onboarding- resources\cpython-main\Doc\c- api\[cpython-main] [Doc] [c- api]call.rst, line 202); backlink Unknown interpreted text role "c:fimc".	PyObject *	1 object	
c:finc:`PyObject_CallObject`			
System Message: ERROR/3 (D:\onboarding- resources\sample-onboarding- resources\cpython-main\Doc\c- api\[cpython-main] [Doc] [c- api] call.rst, line 204); backlink Unknown interpreted text role "c:fimc".	PyObject *	tuple/NULL	
c:func:`PyObject_CallFunction`			
System Message: ERROR/3 (D:\onboarding- resources\sample-onboarding- resources\cpython-main\Doc\c- api\[cpython-main] [Doc] [c- api] call.rst, line 206); backlink Unknown interpreted text role "c:finc".	PyObject *	format	

Function	callable	args	kwargs
c:finc:`PyObject CallMethod`	Canabic	aigs	Kwaigs
System Message: ERROR/3 (D:\onboarding- resources\sample-onboarding- resources\cpython-main\Doc\c- api\[cpython-main] [Doc] [c- api]call.rst, line 208); backlink Unknown interpreted text role "c:finc".	obj+char*	format	
x:fime: PyObject_CallFunctionObjArgs` System Message: ERROR/3 (D:\onboarding- resources\sample-onboarding- resources\cpython-main\Doc\c- api\[cpython-main] [Doc] [c- api] call.rst, line 210); backlink Unknown interpreted text role "c:fime".	PyObject *	variadic	
x:fimc: PyObject_CallMethodObjArgs` System Message: ERROR/3 (D:\onboarding- resources\sample-onboarding- resources\cpython-main\Doc\c- api\[cpython-main][Doc][c- api]call.rst, line 212); backlink Unknown interpreted text role "c:fimc".	obj + name	variadic	
x:fime: PyObject_CallMethodNoArgs` System Message: ERROR/3 (D:\onboarding- resources\sample-onboarding- resources\cpython-main\Doc\c- api\[cpython-main][Doc][c- api]call.rst, line 214); backlink Unknown interpreted text role "c:fime".	obj + name		
x:fime: PyObject_CallMethodOneArg' System Message: ERROR/3 (D:\onboarding- resources\sample-onboarding- resources\cpython-main\Doc\c- api\[cpython-main] [Doc] [c- api] call.rst, line 216); backlink Unknown interpreted text role "c:fime".	obj + name	1 object	
System Message: ERROR/3 (D:\onboarding- resources\sample-onboarding- resources\cpython-main\Doc\c- api\[cpython-main] [Doc] [c- api] call.rst, line 218); backlink Unknown interpreted text role "c:fime".	PyObject *	vectorcall	vectorcall
System Message: ERROR/3 (D:\onboarding- resources\sample-onboarding- resources\cpython-main\Doc\c- api\[cpython-main][Doc][c- api]call.rst, line 220); backlink Unknown interpreted text role "c:fime".	PyObject *	vectorcall	dict/NULL

Function	callable	args	kwargs
c:fine: PyObject_VectorcallMethod` System Message: ERROR/3 (D:\onboarding- resources\sample-onboarding- resources\cpython-main\Doc\c- api\[cpython-main] [Doc] [c- api] call.rst, line 222); backlink Unknown interpreted text role "c:fine".	arg + name	vectorcall	vectorcall

Unknown directive type "c:function".

```
.. c:function:: PyObject* PyObject_Call(PyObject *callable, PyObject *args, PyObject *twargs)

Call a callable Python object *callable*, with arguments given by the tuple *args*, and named arguments given by the dictionary *kwargs*.

*args* must not be *NULL*; use an empty tuple if no arguments are needed.

If no named arguments are needed, *kwargs* can be *NULL*.

Return the result of the call on success, or raise an exception and return *NULL* on failure.
```

This is the equivalent of the Python expression: ``callable(*args, **kwargs)``.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] call.rst, line 240)

Unknown directive type "c:function".

.. c:function:: PyObject* PyObject_CallNoArgs(PyObject *callable)

Call a callable Python object *callable* without any arguments. It is the most efficient way to call a callable Python object without any argument.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

.. versionadded:: 3.9

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] call.rst, line 251)

Unknown directive type "c:function".

.. c:function:: PyObject* PyObject CallOneArg(PyObject *callable, PyObject *arg)

Call a callable Python object *callable* with exactly 1 positional argument *arg* and no keyword arguments.

Return the result of the call on success, or raise an exception and return $^{\star}\mathrm{NULL}^{\star}$ on failure.

This function is not part of the :ref:`limited API <stable>`.

.. versionadded:: 3.9

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] call.rst, line 264)

Unknown directive type "c:function".

```
.. c:function:: PyObject* PyObject_CallObject(PyObject *callable, PyObject *args)
```

Call a callable Python object *callable*, with arguments given by the tuple *args*. If no arguments are needed, then *args* can be *NULL*.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

This is the equivalent of the Python expression: ``callable(*args)``.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] call.rst, line 275)

Unknown directive type "c:function".

.. c:function:: PyObject* PyObject_CallFunction(PyObject *callable, const char *format,

```
Call a callable Python object *callable*, with a variable number of C arguments.
The C arguments are described using a :c:func: 'Py_BuildValue' style format string. The format can be *NULL*, indicating that no arguments are provided.
Return the result of the call on success, or raise an exception and return
*NULL* on failure.
This is the equivalent of the Python expression: ``callable(*args)``.
Note that if you only pass :c:type:`PyObject *` args, :c:func:`PyObject_CallFunctionObjArgs` is a faster alternative.
.. versionchanged:: 3.4
    The type of *format* was changed from ``char *``.
```

main\Doc\c-api\[cpython-main][Doc][c-api]call.rst, line 293)

Unknown directive type "c:function".

```
... c:function:: PyObject* PyObject CallMethod(PyObject *obj, const char *name, const char *format, ...)
   Call the method named *name* of object *obj* with a variable number of {\tt C}
   arguments. The C arguments are described by a :c:func:Py_BuildValue format string that should produce a tuple.
   The format can be *NULL*, indicating that no arguments are provided.
   Return the result of the call on success, or raise an exception and return
   *NULL* on failure.
   This is the equivalent of the Python expression:
    `obj.name(arg1, arg2, ...)``.
   Note that if you only pass :c:type:`PyObject *` args, :c:func:`PyObject_CallMethodObjArgs` is a faster alternative.
   .. versionchanged:: 3.4

The types of *name* and *format* were changed from ``char *``.
```

 $System\,Message:\,ERROR/3\,(\text{D:}\comboarding-resources}) sample-onboarding-resources\\cpython-onboarding-resources$ main\Doc\c-api\[cpython-main][Doc][c-api]call.rst, line 314)

Unknown directive type "c:function".

```
.. c:function:: PyObject* PyObject CallFunctionObjArgs(PyObject *callable, ...)
  Call a callable Python object *callable*, with a variable number of
  :c:type: PyObject *` arguments. The arguments are provided as a variable number of parameters followed by *NULL*.
  Return the result of the call on success, or raise an exception and return
  *NULL* on failure.
  This is the equivalent of the Python expression:
    `callable(arg1, arg2, ...)``
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpythonmain\Doc\c-api\[cpython-main][Doc][c-api]call.rst, line 327)

Unknown directive type "c:function".

```
.. c:function:: PyObject* PyObject CallMethodObjArgs(PyObject *obj, PyObject *name, ..
   Call a method of the Python object *obj*, where the name of the method is given as
   Python string object in *name*. It is called with a variable number of :c:type:`PyObject *` arguments. The arguments are provided as a variable number
   of parameters followed by *NULL*.
   Return the result of the call on success, or raise an exception and return
   *NULL* on failure.
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpythonmain\Doc\c-api\[cpython-main][Doc][c-api]call.rst, line 338)

Unknown directive type "c:function".

```
.. c:function:: PyObject* PyObject_CallMethodNoArgs(PyObject *obj, PyObject *name)
  Call a method of the Python object *obj* without arguments,
  where the name of the method is given as a Python string object in *name*.
  Return the result of the call on success, or raise an exception and return
  *NULL* on failure.
  This function is not part of the :ref: `limited API <stable>`.
   .. versionadded:: 3.9
```

```
System\,Message: ERROR/3~(\texttt{D:\onboarding-resources\backslash sample-onboarding-resources\backslash cpython-onboarding-resources\backslash cpython-onboarding-resources). The state of the 
  ain\Doc\c-api\[cpython-main][Doc][c-api]call.rst, line 351)
Unknown directive type "c:function".
        .. c:function:: PyObject* PyObject CallMethodOneArg(PyObject *obj, PyObject *name, PyObject *arg)
               Call a method of the Python object *obj* with a single positional argument
               *arg*, where the name of the method is given as a Python string object in *name*.
               Return the result of the call on success, or raise an exception and return
               *NULL* on failure.
               This function is not part of the :ref:`limited API <stable>`.
               .. versionadded:: 3.9
System Message: ERROR/3 (D:\onboarding-resources\sam
                                                                                                                                       le-onboarding-resources\cpython-
main\Doc\c-api\[cpython-main][Doc][c-api]call.rst, line 365)
Unknown directive type "c:function".
        .. c:function:: PyObject* PyObject_Vectorcall(PyObject *callable, PyObject *const *args, size_t nargsf, PyObjec
               Call a callable Python object *callable*.
               The arguments are the same as for :c:type:`vectorcallfunc`. If *callable* supports vectorcall_, this directly calls the vectorcall function stored in *callable*.
               Return the result of the call on success, or raise an exception and return
                *NULL* on failure.
               This function is not part of the :ref:`limited API <stable>`.
               .. versionadded:: 3.9
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-
main\Doc\c-api\[cpython-main][Doc][c-api]call.rst, line 379)
Unknown directive type "c:function".
        .. c:function:: PyObject* PyObject_VectorcallDict(PyObject *callable, PyObject *const *args, size_t nargsf, PyO
               Call *callable* with positional arguments passed exactly as in the vectorcall protocol,
               but with keyword arguments passed as a dictionary *kwdict*.
              The *args* array contains only the positional arguments.
               Regardless of which protocol is used internally,
              a conversion of arguments needs to be done. Therefore, this function should only be used if the caller
               already has a dictionary ready to use for the keyword arguments,
              but not a tuple for the positional arguments.
               This function is not part of the :ref:`limited API <stable>`.
               .. versionadded:: 3.9
System\,Message:\,ERROR/3\,(\text{D:}\colored ing-resources}) a mple-onboarding-resources \colored ing-resources) and the state of the colored ing-resources \colored ing-resources \colored ing-resources). The state of the colored ing-resources \colored ing-resources \colored ing-resources \colored ing-resources \colored ing-resources). The state of the colored ing-resources \colored ing-resources \colored ing-resources \colored ing-resources). The state of the colored ing-resources \colored ing-resources 
main\Doc\c-api\[cpython-main][Doc][c-api]call.rst, line 395)
Unknown directive type "c:function".
        .. c:function:: PyObject* PyObject_VectorcallMethod(PyObject *name, PyObject *const *args, size_t nargsf, PyObj
               Call a method using the vectorcall calling convention. The name of the method
               is given as a Python string *name*. The object whose method is called is *args[0]*, and the *args* array starting at *args[1]* represents the arguments
               of the call. There must be at least one positional argument.
              *nargsf* is the number of positional arguments including *args[0]*, plus :const:`PY_VECTORCALL_ARGUMENTS_OFFSET` if the value of ``args
                                                                                                                                                                               args[0]`` may
               temporarily be changed. Keyword arguments can be passed just like in
               :c:func: `PyObject Vectorcall`.
               If the object has the :const: \protect{\protect}{\protect} METHOD_DESCRIPTOR' feature, this will call the unbound method object with the full
               *args* vector as arguments.
               Return the result of the call on success, or raise an exception and return
              This function is not part of the :ref: `limited API <stable>`.
               .. versionadded:: 3.9
```

Call Support API

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] call.rst, line 421)

Unknown directive type "c:function".

.. c:function:: int PyCallable_Check(PyObject *o)

Determine if the object *o* is callable. Return ``1`` if the object is callable and ``0`` otherwise. This function always succeeds.