# Using Python on Unix platforms

```
System Message: ERROR/3 (p:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\using\(cpython-main\) (Doc) (using) unix.rst, line 1)
Unknown directive type "highlight".
.. highlight:: sh
```

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\using\((cpython-main)\) (Doc) (using) unix.rst, line 9)

Unknown directive type "sectionauthor".

.. sectionauthor:: Shriphani Palakodety
```

# Getting and installing the latest version of Python

#### On Linux

Python comes preinstalled on most Linux distributions, and is available as a package on all others. However there are certain features you might want to use that are not available on your distro's package. You can easily compile the latest version of Python from source.

In the event that Python doesn't come preinstalled and isn't in the repositories as well, you can easily make packages for your own distro. Have a look at the following links:

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\using\(cpython-main\) (Doc) (using) unix.rst, line 27)

Unknown directive type "seeako".

... seealso::

https://www.debian.org/doc/manuals/maint-guide/first.en.html
for Debian users
https://en.opensuse.org/Portal:Packaging
for OpenSuse users
https://docs-old.fedoraproject.org/en-US/Fedora_Draft_Documentation/0.1/html/RPM_Guide/ch-creating-rp
for Fedora users
http://www.slackbook.org/html/package-management-making-packages.html
for Slackware users
```

#### On FreeBSD and OpenBSD

• FreeBSD users, to add the package use:

```
pkg install python3
```

• OpenBSD users, to add the package use:

```
pkg_add -r python
pkg_add ftp://ftp.openbsd.org/pub/OpenBSD/4.2/packages/<insert your architecture here>/python-<version>.t
```

For example i386 users get the 2.5.1 version of Python using:

```
pkg_add ftp://ftp.openbsd.org/pub/OpenBSD/4.2/packages/i386/python-2.5.1p2.tgz
```

#### On OpenSolaris

You can get Python from OpenCSW. Various versions of Python are available and can be installed with e.g. pkgutil -i python27.

# **Building Python**

If you want to compile CPython yourself, first thing you should do is get the source. You can download either the latest release's source or just grab a fresh clone. (If you want to contribute patches, you will need a clone.)

The build process consists of the usual commands:

```
./configure make make install
```

ref: Configuration options < configure-options > and caveats for specific Unix platforms are extensively documented in the source: README.rst' file in the root of the Python source tree.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\using\((cpython-main)\) (Doc) (using) unix.rst, line 81); backlink

Unknown interpreted text role "ref".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\using\((cpython-main)\) (Doc) (using) unix.rst, line 81); backlink

Unknown interpreted text role "source".

#### Warning

make install can overwrite or masquerade the :file: python3` binary. make altinstall is therefore recommended instead of make install since it only installs :file: {exec prefix}/bin/python{version}`.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\using\(cpython-main\) (Doc) (using) unix.rst, line 87); backlink

Unknown interpreted text role "file".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\using\(cpython-main\) (Doc) (using) unix.rst, line 87); backlink

Unknown interpreted text role "file".

## Python-related paths and files

These are subject to difference depending on local installation conventions; :envar:`prefix`(\${prefix}) and :envar:`exec\_prefix`
(\${prefix}) are installation-dependent and should be interpreted as for GNU software; they may be the same.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\using\((cpython-main)\) (Doc) (using) unix.rst, line 95); backlink

Unknown interpreted text role "envvar".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\using\((cpython-main)\) (Doc) (using) unix.rst, line 95); backlink

Unknown interpreted text role "envvar".

For example, on most Linux systems, the default for both is :file:'/usr'.

 $System\,Message:\,ERROR/3\, (\mboarding-resources\spaces) convolves ample-onboarding-resources\spaces convolves and the convolves ample-onboarding-resources convolves and the convolves are convolved as a convolve convolves and the convolves are convolved as a convolve convolves and the convolves are convolved as a convolve convolves and the convolves are convolved as a convolve convolves and the convolves are convolved as a convolve convolves and the convolves are convolved as a convolve convolves and the convolves are convolved as a convolve convolves and the convolves are convolved as a convolve convolves and the convolves are convolved as a convolve convolves and the convolves are convolved as a convolve convolves and the convolves are convolved as a convolve convolve convolves and the convolves are convolved as a convolve convolve convolves and the convolves are convolved as a convolve convolve convolves and the convolves are convolved as a convolve convolve convolves and the convolve convolves are convolved as a convolve convolve convolve convolve convolve convolve convolves are convolved as a convolve conv$ 

Unknown interpreted text role "file".

e/directory	Meaning
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\using\((cpython-main) (Doc) (using) unix.rst, line 106); backlink  Unknown interpreted text role "file".	Recommended location of the interpreter.

File/directory Meaning :file:`{prefix}/lib/python{version}`, :file:\{exec prefix\}/lib/python\{version\}\ System Message: ERROR/3 (D:\onboardingresources\sample-onboardingresources\cpython-main\Doc\using\ (cpython-main) (Doc) (using) unix.rst, line 108); backlink Recommended locations of the directories containing the Unknown interpreted text role "file". standard modules. System Message: ERROR/3 (D:\onboardingresources\sample-onboardingresources\cpython-main\Doc\using\ (cpython-main) (Doc) (using) unix.rst, line 108); backlink Unknown interpreted text role "file". :file:`{prefix}/include/python{version}`, :file:`{exec prefix}/include/python{version}` System Message: ERROR/3 (D:\onboardingresources\sample-onboardingresources\cpython-main\Doc\using\ (cpython-main) (Doc) (using) unix.rst, line 111); backlink Recommended locations of the directories containing the Unknown interpreted text role "file". include files needed for developing Python extensions and embedding the interpreter. System Message: ERROR/3 (D:\onboardingresources\sample-onboardingresources\cpython-main\Doc\using\ (cpython-main) (Doc) (using) unix.rst, line 111); backlink Unknown interpreted text role "file".

## Miscellaneous

To easily use Python scripts on Unix, you need to make them executable, e.g. with

```
$ chmod +x script
```

and put an appropriate Shebang line at the top of the script. A good choice is usually

```
#!/usr/bin/env python3
```

which searches for the Python interpreter in the whole :envvar: 'PATH'. However, some Unices may not have the :program: 'env' command, so you may need to hardcode /usr/bin/python3 as the interpreter path.

 $System\ Message: ERROR/3\ (D:\onboarding-resources\spaces) converges converges converges and the converges converges converges and the converges converges converges and the converges converges converges and the converges converges converges converges and the converges converges and the converges converges c$ 

Unknown interpreted text role "envvar".

Unknown interpreted text role "program".

To use shell commands in your Python scripts, look at the <a href="mod:"subprocess">module</a>.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\using\((cpython-main)\) (Doc) (using) unix.rst, line 136); backlink

Unknown interpreted text role "mod".

# **Custom OpenSSL**

1. To use your vendor's OpenSSL configuration and system trust store, locate the directory with openssl.cnf file or symlink in /etc. On most distribution the file is either in /etc/ssl or /etc/pki/tls. The directory should also contain a

cert.pem file and/or a certs directory.

```
$ find /etc/ -name openssl.cnf -printf "%h\n"
/etc/ssl
```

2. Download, build, and install OpenSSL. Make sure you use install\_sw and not install. The install\_sw target does not override openssl.cnf.

3. Build Python with custom OpenSSL (see the configure --with-openssl and --with-openssl-rpath options)

```
$ pushd python-3.x.x
$ ./configure -C \
    --with-openssl=/usr/local/custom-openssl \
    --with-openssl-rpath=auto \
    --prefix=/usr/local/python-3.x.x
$ make -j8
$ make altinstall
```

#### Note

Patch releases of OpenSSL have a backwards compatible ABI. You don't need to recompile Python to update OpenSSL. It's sufficient to replace the custom OpenSSL installation with a newer version.