# ioctl VIDIOC CROPCAP

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-
master\Documentation\userspace-api\media\v41\(linux-master)\(Documentation\)\(userspace-api\)\((media\)\(v41)\vidioc-cropcap.rst,\(line 2\)\)
Unknown directive type "cnamespace".

.. c:namespace:: V4L
```

### Name

VIDIOC CROPCAP - Information about the video cropping and scaling abilities

## **Synopsis**

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-
master\Documentation\userspace-api\media\v41\(linux-master) (Documentation) (userspace-
api) (media) (v41) vidioc-cropcap.rst, line 18)

Unknown directive type "c:macro".

.. c:macro:: VIDIOC_CROPCAP
```

int ioctl(int fd, VIDIOC CROPCAP, struct v412 cropcap \*argp)

### **Arguments**

fd

File descriptor returned by :c:func:'open()'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\((linux-master)\) (Documentation) (userspace-api) (media) (v41) vidioc-cropcap.rst, line 26); backlink Unknown interpreted text role "c:func".

argp

Pointer to struct :c:type:\v412\_cropcap\.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\((linux-master)\) (Documentation) (userspace-api) (media) (v41) vidioc-cropcap.rst, line 29); backlink Unknown interpreted text role "c:type".

# **Description**

Applications use this function to query the cropping limits, the pixel aspect of images and to calculate scale factors. They set the type field of a v4l2\_cropcap structure to the respective buffer (stream) type and call the ref: video can call the video ioctl with a pointer to this structure. Drivers fill the rest of the structure. The results are constant except when switching the video standard. Remember this switch can occur implicit when switching the video input or output.

 $System\ Message:\ ERROR/3\ (\mbox{D:\noboarding-resources\sample-onboarding-resources\linux-master)}\ (\mbox{Documentation}\subseteq\api)\ (\mbox{media}\subseteq\api)\ (\mbox{media}\subset$ 

Unknown interpreted text role 'ref'.

This ioctl must be implemented for video capture or output devices that support cropping and/or scaling and/or have non-square pixels, and for overlay devices.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master) (Documentation) (userspace-api) (media) (v41) vidioc-cropcap.rst, line 46)
Unknown directive type "c:type".

.. c:type:: v4l2 cropcap

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master) (Documentation) (userspace-api) (media) (v41) vidioc-cropcap.rst, line 48)

Unknown directive type "tabularcolumns".

.. tabularcolumns::  $|p{4.4cm}|p{4.4cm}|p{8.5cm}|$ 

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master) (Documentation) (userspace-api) (media) (v41) vidioc-cropcap.rst, line 50)

Unknown directive type "flat-table".

```
.. flat-table:: struct v412_cropcap
   :header-rows: 0
   :stub-columns: 0
    :widths:
                    1 1 2
      - __u32
- ``type``
      - Type of the data stream, set by the application. Only these types
        are valid here: ``V4L2_BUF_TYPE_VIDEO_CAPTURE``, ``V4L2_BUF_TYPE_VIDEO_CAPTURE MPLANE``,
          `V4L2_BUF_TYPE_VIDEO_OUTPUT``, ``V4L2_BUF_TYPE_VIDEO_OUTPUT_MPLANE`` and `V4L2_BUF_TYPE_VIDEO_OVERLAY``. See :c:type:`v4l2_buf_type` and the note below.
        ``V4L2_BUF_
    * - struct :ref: `v412 rect <v412-rect-crop>
      - ``bounds`
      - Defines the window within capturing or output is possible, this
        may exclude for example the horizontal and vertical blanking
        areas. The cropping rectangle cannot exceed these limits. Width
        and height are defined in pixels, the driver writer is free to
        choose origin and units of the coordinate system in the analog
        domain.
    * - struct :ref: `v412 rect <v412-rect-crop>`
       ``defrect
      - Default cropping rectangle, it shall cover the "whole picture".
        Assuming pixel aspect 1/1 this could be for example a 640 \mbox{\em A-}\ 480
        rectangle for NTSC, a 768 \tilde{A}- 576 rectangle for PAL and SECAM
        centered over the active picture area. The same co-ordinate system
       as for ``bounds`` is used.
    * - struct :c:type:`v412_fract`
      - ``pixelaspect`
```

#### Note

Unfortunately in the case of multiplanar buffer types (V4L2\_BUF\_TYPE\_VIDEO\_CAPTURE\_MPLANE and V4L2\_BUF\_TYPE\_VIDEO\_OUTPUT\_MPLANE) this API was messed up with regards to how the :c:type: V4l2\_cropcap` type field should be filled in. Some drivers only accepted the \_MPLANE buffer type while other drivers only accepted a non-multiplanar buffer type (i.e. without the \_MPLANE at the end).

- This is the pixel aspect (y / x) when no scaling is applied, the ratio of the actual sampling frequency and the frequency required

When cropping coordinates refer to square pixels, the driver sets ``pixelaspect`` to 1/1. Other common values are 54/59 for PAL and SECAM, 11/10 for NTSC sampled according to [:ref:`itu601`].

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master) (Documentation) (userspace-api) (media) (v41) vidioc-cropcap.rst, line 87); backlink

Unknown interpreted text role "c:type".

to get square pixels.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master\) (Documentation) (userspace-api) (media) (v41) vidioc-cropcap.rst, line 99)

Unknown directive type "tabularcolumns".

.. tabularcolumns:: |p{4.4cm}|p{4.4cm}|p{8.5cm}|

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master) (Documentation) (userspace-api) (media) (v41) vidioc-cropcap.rst, line 101)
Unknown directive type "flat-table".

### Return Value

On success 0 is returned, on error -1 and the errno variable is set appropriately. The generic error codes are described at the ref. Generic Error Codes <gen-errors>` chapter.

 $System \, Message: ERROR/3 \, (\mbox{D:\noboarding-resources\sample-onboarding-resources\linux-master)} \, (\mbox{Documentation}) \, (\mbox{Documentation}) \, (\mbox{userspace-api}) \, (\mbox{media}) \, (\mbox{v41}) \, (\mbox{Dinux-master}) \, (\mbox{Documentation}) \, (\mbox{userspace-api}) \, (\mbox{media}) \, (\mbox{v41}) \, (\mbox{Dinux-master}) \, (\mbox{Documentation}) \, (\mbox{userspace-api}) \, (\mbox{media}) \, (\mbox{v41}) \, (\mbox{Dinux-master}) \, (\mbox{Documentation}) \, (\mbox{userspace-api}) \, (\mbox{media}) \, (\mbox{v41}) \, (\mbox{Dinux-master}) \, (\mbox{Documentation}) \, (\mbox{userspace-api}) \, (\mbox{media}) \, (\mbox{v41}) \, (\mbox{Dinux-master}) \, (\mbox{Documentation}) \, (\mbox{userspace-api}) \, (\mbox{media}) \, (\mbox{v41}) \, (\mbox{Dinux-master}) \, (\mbox{Documentation}) \, (\mbox{userspace-api}) \, (\mbox{media}) \, (\mbox{v41}) \, (\mbox{Dinux-master}) \, (\mbox{Documentation}) \, (\mbox{userspace-api}) \, (\mbox{media}) \, (\mbox{v41}) \, (\mbox{Dinux-master}) \, (\mbox{Documentation}) \, (\mbox{userspace-api}) \, (\mbox{media}) \, (\mbox{v41}) \, (\mbox{Dinux-master}) \, (\mbox{Documentation}) \, (\mbox{userspace-api}) \, (\mbox{media}) \, (\mbox{v41}) \, (\mbox{Dinux-master}) \, (\mbox{Documentation}) \, (\mbox{userspace-api}) \, (\mbox{media}) \, (\mbox{v41}) \, (\mbox{Dinux-master}) \, (\mbox{Documentation}) \, (\mbox{userspace-api}) \, (\mbox{media}) \, (\mbox{v41}) \, (\mbox{Dinux-master}) \, (\mbox{Documentation}) \, (\mbox{userspace-api}) \, (\mbox{media}) \, (\mbox{v41}) \, (\mbox{Dinux-master}) \, (\mbox{Documentation}) \, (\mbox{userspace-api}) \, (\mbox{media}) \, (\mbox{v41}) \, (\mbox{Dinux-master}) \, (\mbox{Documentation}) \, (\mbox{userspace-api}) \, (\mbox{media}) \, (\mbox{Documentation}) \, (\mbox{Documen$ 

Unknown interpreted text role "ref".

### **EINVAL**

The struct :c:type:\v412\_cropcap\`type is invalid.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master) (Documentation) (userspace-api) (media) (v41) vidioc-cropcap.rst, line 129); backlink

Unknown interpreted text role "c:type".

### **ENODATA**

Cropping is not supported for this input or output.