ioctl VIDIOC_SUBSCRIBE_EVENT, VIDIOC UNSUBSCRIBE EVENT

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] vidioc-subscribe-event.rst, line 2)

Unknown directive type "c:namespace".

.. c:namespace:: V4L

Name

VIDIOC SUBSCRIBE EVENT - VIDIOC UNSUBSCRIBE EVENT - Subscribe or unsubscribe event

Synopsis

 $System\ Message: ERROR/3\ (\mbox{D:\noboarding-resources}\scample-onboarding-resources\linux-master\Documentation\userspace-api\mbox{media}\v41\[linux-master\]\[Documentation\]\ [userspace-api\]\ [media\]\ [v41]\vidioc-subscribe-event.rst,\ line\ 19)$

Unknown directive type "c:macro".

.. c:macro:: VIDIOC SUBSCRIBE EVENT

int ioctl(int fd, VIDIOC SUBSCRIBE EVENT, struct v412 event subscription *argp)

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] vidioc-subscribe-event.rst, line 23)

Unknown directive type "c:macro".

.. c:macro:: VIDIOC_UNSUBSCRIBE_EVENT

int ioctl(int fd, VIDIOC UNSUBSCRIBE EVENT, struct v412 event subscription *argp)

Arguments

fd

File descriptor returned by :c:func:'open()'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] vidioc-subscribe-event.rst, line 31); backlink

Unknown interpreted text role "c:func".

argp

Pointer to struct :c:type: v412 event subscription.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] vidioc-subscribe-event.rst, line 34); backlink

Unknown interpreted text role "c:type".

Description

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] vidioc-subscribe-event.rst, line 39); backlink

Unknown interpreted text role 'ref'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] vidioc-subscribe-event.rst, line 42)

Unknown directive type "tabularcolumns".

```
.. tabularcolumns:: |p{2.6cm}|p{4.4cm}|p{10.3cm}|
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] vidioc-subscribe-event.rst, line 44)

Unknown directive type "c:type".

```
.. c:type:: v4l2 event subscription
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] vidioc-subscribe-event.rst, line 46)

Unknown directive type "flat-table".

```
.. flat-table:: struct v412 event subscription
   :header-rows: 0
   :stub-columns: 0
                   1 1 2
   :widths:
    * - __u32
- ``type``
      - Type of the event, see :ref:`event-type`.
        .. note::
           ``V4L2 EVENT ALL`` can be used with
           :ref:`VIDIOC UNSUBSCRIBE EVENT <VIDIOC SUBSCRIBE EVENT>` for
           unsubscribing all events at once.
         u32
       ~id`
      - ID of the event source. If there is no ID associated with the
        event source, then set this to 0. Whether or not an event needs an
       ID depends on the event type.
    * - _u32
- ``flags`
      - Event flags, see :ref:`event-flags`.
    * - _u32
- ``reserved``\ [5]
      - Reserved for future extensions. Drivers and applications must set
        the array to zero.
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] vidioc-subscribe-event.rst, line 74)

Unknown directive type "tabularcolumns".

```
.. tabularcolumns:: |p{7.5cm}|p{2.0cm}|p{7.8cm}|
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] vidioc-subscribe-event.rst, line 78)

Unknown directive type "flat-table".

```
.. flat-table:: Event Flags
    :header-rows: 0
    :stub-columns: 0
    :widths:
                3 1 4
    * - ``V4L2_EVENT_SUB_FL_SEND_INITIAL``
      -0x0001
      - When this event is subscribed an initial event will be sent
        containing the current status. This only makes sense for events that are triggered by a status change such as ``V4L2_EVENT_CTRL``.
        Other events will ignore this flag.
    * - ``V4L2_EVENT_SUB_FL_ALLOW_FEEDBACK``
      -0x0002
      - If set, then events directly caused by an ioctl will also be sent
        to the filehandle that called that ioctl. For example, changing a
        control using :ref:`VIDIOC_S_CTRL <VIDIOC_G_CTRL>` will cause
        a V4L2 EVENT CTRL to be sent back to that same filehandle.
        Normally such events are suppressed to prevent feedback loops
        where an application changes a control to a one value and then
        another, and then receives an event telling it that that control
        has changed to the first value.
        Since it can't tell whether that event was caused by another application or by the :ref: \VIDIOC_S\_CTRL < \VIDIOC\_G\_CTRL>`
        call it is hard to decide whether to set the control to the value
        in the event, or ignore it.
        Think carefully when you set this flag so you won't get into
```

Return Value

On success 0 is returned, on error -1 and the errno variable is set appropriately. The generic error codes are described at the ref. Generic Error Codes <gen-errors>` chapter.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] vidioc-subscribe-event.rst, line 111); backlink

Unknown interpreted text role 'ref'.

situations like that.