Module Objects

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] module.rst, line 1)
```

Unknown directive type "highlight".

```
.. highlight:: c
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] module.rst, line 8)

Unknown directive type "index".

```
.. index:: object: module
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api]module.rst, line 11)

Unknown directive type "c:var".

```
.. c:var:: PyTypeObject PyModule_Type
.. index:: single: ModuleType (in module types)

This instance of :c:type:`PyTypeObject` represents the Python module type. This is exposed to Python programs as ``types.ModuleType``.
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api]module.rst, line 19)

Unknown directive type "c:function".

```
.. c:function:: int PyModule_Check(PyObject *p)

Return true if *p* is a module object, or a subtype of a module object.
This function always succeeds.
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[continue] [continue] [continue]

Unknown directive type "c:function".

```
.. c:function:: int PyModule_CheckExact(PyObject *p)

Return true if *p* is a module object, but not a subtype of
:c:data:`PyModule_Type`. This function always succeeds.
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] module.rst, line 31)

Unknown directive type "c:function".

```
c:function:: PyObject* PyModule_NewObject(PyObject *name)

.. index::
    single: __name__ (module attribute)
    single: __doc__ (module attribute)
    single: __file__ (module attribute)
    single: __package__ (module attribute)

Return a new module object with the :attr:`__name__` attribute set to *name*.
The module's :attr:`_name__`, :attr:`_doc__`, :attr:`_package__`, and
    :attr:`_loader__` attributes are filled in (all but :attr:`_name__` are set to ``None``); the caller is responsible for providing a :attr:`_file__`
attribute.

.. versionadded:: 3.3

.. versionchanged:: 3.4
    :attr:`__package__` and :attr:`__loader__` are set to ``None``.
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpythonmain\Doc\c-api\[cpython-main][Doc][c-api]module.rst, line 52)

Unknown directive type "c:function".

.. c:function:: PyObject* PyModule New(const char *name) Similar to :c:func:`PyModule NewObject`, but the name is a UTF-8 encoded string instead of a Unicode object.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpythonmain\Doc\c-api\[cpython-main][Doc][c-api]module.rst, line 58)

Unknown directive type "c:function".

```
.. c:function:: PyObject* PyModule_GetDict(PyObject *module)
   .. index:: single: dict (module attribute)
  Return the dictionary object that implements *module*'s namespace; this object
  is the same as the :attr:`~object.__dict__` attribute of the module object.
  If *module* is not a module object (or a subtype of a module object), :exc: SystemError` is raised and ``NULL`` is returned.
  It is recommended extensions use other :c:func:`PyModule\' and
   :c:func:`PyObject_\` functions rather than directly manipulate a module's
   :attr:`~object.__dict__`.
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpythonmain\Doc\c-api\[cpython-main][Doc][c-api]module.rst, line 72)

Unknown directive type "c:function".

```
.. c:function:: PyObject* PyModule_GetNameObject(PyObject *module)
    .. index::
                    name
                             (module attribute)
       single: SystemError (built-in exception)
   Return *module*'s :attr:`__name__` value. If the module does not provide one, or if it is not a string, :exc:`SystemError` is raised and ``NULL`` is returne
    .. versionadded:: 3.3
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpythonmain\Doc\c-api\[cpython-main][Doc][c-api]module.rst, line 84)

Unknown directive type "c:function".

```
.. c:function:: const char* PyModule GetName(PyObject *module)
  Similar to :c:func:`PyModule GetNameObject` but return the name encoded to
    `'utf-8'`
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpythonmain\Doc\c-api\[cpython-main][Doc][c-api]module.rst, line 89)

Unknown directive type "c:function".

```
.. c:function:: void* PyModule_GetState(PyObject *module)
   Return the "state" of the module, that is, a pointer to the block of memory allocated at module creation time, or ``NULL``. See
   :c:member:`PyModuleDef.m_size`.
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpythonmain\Doc\c-api\[cpython-main][Doc][c-api]module.rst, line 96)

Unknown directive type "c:function".

```
.. c:function:: PyModuleDef* PyModule GetDef(PyObject *module)
  Return a pointer to the :c:type:`PyModuleDef` struct from which the module was
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[continue] [continue] [continue]

Unknown directive type "c:function".

```
.. c:function:: PyObject* PyModule_GetFilenameObject(PyObject *module)
.. index::
    single: __file__ (module attribute)
    single: SystemError (built-in exception)

Return the name of the file from which *module* was loaded using *module*'s
:attr:`_file__` attribute. If this is not defined, or if it is not a
unicode string, raise :exc:`SystemError` and return ``NULL``; otherwise return
a reference to a Unicode object.
.. versionadded:: 3.2
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[continue] [continue] [continue]

Unknown directive type "c:function".

```
    c:function:: const char* PyModule_GetFilename(PyObject *module)
    Similar to :c:func:`PyModule_GetFilenameObject` but return the filename encoded to 'utf-8'.
    deprecated:: 3.2
    :c:func:`PyModule_GetFilename` raises :c:type:`UnicodeEncodeError` on unencodable filenames, use :c:func:`PyModule_GetFilenameObject` instead.
```

Initializing C modules

Modules objects are usually created from extension modules (shared libraries which export an initialization function), or compiled-in modules (where the initialization function is added using :c:func:'PyImport_AppendInittab'). See ref:'building' or :ref:'extending-withembedding' for details.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main][Doc][c-api]module.rst, line 131); backlink
```

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] module.rst, line 131); backlink

Unknown interpreted text role 'ref'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] module.rst, line 131); backlink

Unknown interpreted text role "ref".

The initialization function can either pass a module definition instance to :c:func:`PyModule_Create`, and return the resulting module object, or request "multi-phase initialization" by returning the definition struct itself.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] module.rst, line 136); backlink

Unknown interpreted text role "c:func".

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api]module.rst, line 140)
```

Unknown directive type "c:type".

```
.. c:type:: PyModuleDef
```

The module definition struct, which holds all information needed to create a module object. There is usually only one statically initialized variable of this type for each module.

```
.. c:member:: PyModuleDef_Base m_base
  Always initialize this member to :const: `PyModuleDef_HEAD_INIT`.
.. c:member:: const char *m name
  Name for the new module.
.. c:member:: const char *m doc
  Docstring for the module; usually a docstring variable created with
  :c:macro:`PyDoc_STRVAR` is used.
.. c:member:: Py_ssize_t m_size
  Module state may be kept in a per-module memory area that can be
  retrieved with :c:func:`PyModule GetState`, rather than in static globals.
  This makes modules safe for use in multiple sub-interpreters.
  This memory area is allocated based on *m size* on module creation.
  and freed when the module object is deallocated, after the
  :c:member:`m_free` function has been called, if present.
  Setting ``m_size`` to ``-1`` means that the module does not support
  sub-interpreters, because it has global state.
  Setting it to a non-negative value means that the module can be
  re-initialized and specifies the additional amount of memory it requires for its state. Non-negative ``m_size`` is required for multi-phase
  initialization.
  See :PEP: `3121` for more details.
.. c:member:: PyMethodDef* m_methods
  A pointer to a table of module-level functions, described by
  :c:type:`PyMethodDef` values. Can be ``NULL`` if no functions are present.
.. c:member:: PyModuleDef Slot* m slots
  An array of slot definitions for multi-phase initialization, terminated by
  a ``{0, NULL}`` entry.
  When using single-phase initialization, *m slots* must be ``NULL``.
  .. versionchanged:: 3.5
     Prior to version 3.5, this member was always set to ``NULL``,
     and was defined as:
        .. c:member:: inquiry m reload
.. c:member:: traverseproc m traverse
  A traversal function to call during GC traversal of the module object, or
   ``NULL`` if not needed.
  This function is not called if the module state was requested but is not
  allocated yet. This is the case immediately after the module is created
  and before the module is executed (:c:data:`Py\_mod\_exec` function). More
  precisely, this function is not called if :c:member:`m size` is greater
  than 0 and the module state (as returned by :c:func:`PyModule_GetState`) is ``NULL``.
   .. versionchanged:: 3.9
     No longer called before the module state is allocated.
.. c:member:: inquiry m clear
  A clear function to call during GC clearing of the module object, or
    `NULL`` if not needed.
  This function is not called if the module state was requested but is not
  allocated yet. This is the case immediately after the module is created
  and before the module is executed (:c:data:`Py_mod_exec` function). More
  precisely, this function is not called if :c:member:`m_size` is greater
  than 0 and the module state (as returned by :c:func:`PyModule_GetState`)
       `NULL`
  Like :c:member: `PyTypeObject.tp clear`, this function is not *always*
  called before a module is deallocated. For example, when reference
  counting is enough to determine that an object is no longer used,
  the cyclic garbage collector is not involved and
  :c:member:`~PyModuleDef.m_free` is called directly.
  .. versionchanged:: 3.9
     No longer called before the module state is allocated.
.. c:member:: freefunc m free
  A function to call during deallocation of the module object, or ``NULL``
```

```
if not needed.
This function is not called if the module state was requested but is not
allocated yet. This is the case immediately after the module is created
and before the module is executed (:c:data:`Py mod exec` function). More
precisely, this function is not called if :c:member: `m size` is greater
than 0 and the module state (as returned by :c:func: `PyModule GetState`)
is ``NULL``.
.. versionchanged:: 3.9
  No longer called before the module state is allocated.
```

Single-phase initialization

The module initialization function may create and return the module object directly. This is referred to as "single-phase initialization", and uses one of the following two module creation functions:

```
System\,Message:\,ERROR/3\, (\texttt{D:} \verb|\conting-resources| sample-onboarding-resources| cpython-onboarding-resources| conting-resources| conting-reso
main\Doc\c-api\[cpython-main][Doc][c-api]module.rst, line 255)
Unknown directive type "c:function".
                    .. c:function:: PyObject* PyModule_Create(PyModuleDef *def)
                                     Create a new module object, given the definition in *def*. This behaves
                                     like :c:func: `PyModule Create2` with *module api version* set to
                                     :const: `PYTHON API VERSION`.
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpythonmain\Doc\c-api\[cpython-main][Doc][c-api]module.rst, line 262)

Unknown directive type "c:function".

```
.. c:function:: PyObject* PyModule Create2(PyModuleDef *def, int module api version)
  Create a new module object, given the definition in *def*, assuming the
  API version *module api version*. If that version does not match the version
  of the running interpreter, a :exc:`RuntimeWarning` is emitted.
   .. note::
     Most uses of this function should be using :c:func:`PyModule Create`
     instead; only use this if you are sure you need it.
```

Before it is returned from in the initialization function, the resulting module object is typically populated using functions like :c:func:`PyModule AddObjectRef.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-
main\Doc\c-api\[cpython-main][Doc][c-api]module.rst, line 273); backlink
Unknown interpreted text role "c:func".
```

Multi-phase initialization

An alternate way to specify extensions is to request "multi-phase initialization". Extension modules created this way behave more like Python modules: the initialization is split between the creation phase, when the module object is created, and the execution phase, when it is populated. The distinction is similar to the "py:meth:" __new__ ` and "py:meth: `__init__ ` methods of classes.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-
main\Doc\c-api\[cpython-main][Doc][c-api]module.rst, line 281); backlink
Unknown interpreted text role "py:meth".
```

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-
main\Doc\c-api\[cpython-main][Doc][c-api]module.rst, line 281); backlink
```

Unknown interpreted text role "py:meth".

Unlike modules created using single-phase initialization, these modules are not singletons: if the sys. modules entry is removed and the module is re-imported, a new module object is created, and the old module is subject to normal garbage collection -- as with Python modules. By default, multiple modules created from the same definition should be independent: changes to one should not affect the others. This means that all state should be specific to the module object (using e.g. using :c:func: PyModule GetState'), or its contents (such as the module's :attr: __dict__ ` or individual classes created with :c:func: `PyType_FromSpec`).

 $System\,Message:\,ERROR/3\, (\texttt{D:} \verb|\conting-resources| sample-onboarding-resources| cpython-onboarding-resources| conting-resources| conting-reso$

```
main\Doc\c-api\[cpython-main][Doc][c-api]module.rst, line 288); backlink Unknown interpreted text role "c:fimc".
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api]module.rst, line 288); backlink

Unknown interpreted text role "attr".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api]module.rst, line 288); backlink

Unknown interpreted text role "c:func".

All modules created using multi-phase initialization are expected to support ref: sub-interpreters <sub-interpreter-support>`. Making sure multiple modules are independent is typically enough to achieve this.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api]module.rst, line 298); backlink
```

Unknown interpreted text role 'ref'.

To request multi-phase initialization, the initialization function (PyInit_modulename) returns a ctype: PyModuleDef instance with non-empty cmember: ~PyModuleDef.m_slots`. Before it is returned, the PyModuleDef instance must be initialized with the following function:

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] module.rst, line 302); backlink

Unknown interpreted text role "c:type".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[contine=1] [Doc] [c-api] module.rst, line 302); backlink

Unknown interpreted text role "c:member".

 $System\,Message:\,ERROR/3\, (\mbox{D:\nonline}) \label{lem:control} $$ \end{control} $$$ \end{control}$

Unknown directive type "c:function".

```
.. c:function:: PyObject* PyModuleDef_Init(PyModuleDef *def)
    Ensures a module definition is a properly initialized Python object that
    correctly reports its type and reference count.
    Returns *def* cast to ``PyObject*``, or ``NULL`` if an error occurred.
    .. versionadded:: 3.5
```

The *m_slots* member of the module definition must point to an array of PyModuleDef_Slot structures:

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[continue] [Doc] [c-api]module.rst, line 319)

Unknown directive type "c:type".

```
.. c:type:: PyModuleDef_Slot
.. c:member:: int slot
A slot ID, chosen from the available values explained below.
.. c:member:: void* value
Value of the slot, whose meaning depends on the slot ID.
.. versionadded:: 3.5
```

The m slots array must be terminated by a slot with id 0.

The available slot types are:

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api]module.rst, line 335)

Unknown directive type "c:macro".

```
.. c:macro:: Py_mod_create
           Specifies a function that is called to create the module object itself.
           The *value* pointer of this slot must point to a function of the signature:
             .. c:function:: PyObject* create module(PyObject *spec, PyModuleDef *def)
           The function receives a :py:class:`~importlib.machinery.ModuleSpec`
           instance, as defined in :PEP: `451`, and the module definition.
           It should return a new module object, or set an error % \left( 1\right) =\left( 1\right) \left( 1\right) +\left( 1\right) \left( 1\right) \left( 1\right) +\left( 1\right) \left( 1
                                                                   `NULL.`
           and return
           This function should be kept minimal. In particular, it should not
           call arbitrary Python code, as trying to import the same module again may
           result in an infinite loop.
           Multiple ``Py mod create`` slots may not be specified in one module
           definition.
          If ``Py_mod_create`` is not specified, the import machinery will create a normal module object using :c:func:`PyModule_New`. The name is taken from
            {\rm ^*spec^*},\ {\rm not}\ {\rm the\ definition},\ {\rm to\ allow\ extension\ modules\ to\ dynamically\ adjust}
           to their place in the module hierarchy and be imported under different
           names through symlinks, all while sharing a single module definition.
           There is no requirement for the returned object to be an instance of
             :c:type:`PyModule_Type`. Any type can be used, as long as it supports
             setting and getting import-related attributes.
           However, only ``PyModule Type`` instances may be returned if the ``PyModuleDef`` has non-``NULL`` ``m_traverse``, ``m_clear``,
             ``m free``; non-zero ``m size``; or slots other than ``Py mod create``.
```

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api]module.rst, line 367)

Unknown directive type "cmacro".

.. c:macro:: Py_mod_exec

Specifies a function that is called to *execute* the module.
This is equivalent to executing the code of a Python module: typically, this function adds classes and constants to the module.
The signature of the function is:

.. c:function:: int exec_module(PyObject* module)

If multiple ``Py_mod_exec`` slots are specified, they are processed in the order they appear in the *m slots* array.
```

See PEP 489 for more details on multi-phase initialization.

Low-level module creation functions

The following functions are called under the hood when using multi-phase initialization. They can be used directly, for example when creating module objects dynamically. Note that both PyModule_FromDefAndSpec and PyModule_ExecDef must be called to fully initialize a module.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-
main\Doc\c-api\[cpython-main][Doc][c-api]module.rst, line 389)
Unknown directive type "c:function".

.. c:function:: PyObject * PyModule_FromDefAndSpec(PyModuleDef *def, PyObject *spec)

Create a new module object, given the definition in *module* and the
    ModuleSpec *spec*. This behaves like :c:func:`PyModule_FromDefAndSpec2`
    with *module_api_version* set to :const:`PYTHON_API_VERSION`.

.. versionadded:: 3.5
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-

```
Most uses of this function should be using :c:func:`PyModule FromDefAndSpec`
  instead; only use this if you are sure you need it.
.. versionadded:: 3.5
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpythonmain\Doc\c-api\[cpython-main][Doc][c-api]module.rst, line 411)

Unknown directive type "c:function".

```
.. c:function:: int PyModule_ExecDef(PyObject *module, PyModuleDef *def)
  Process any execution slots (:c:data:`Py_mod_exec`) given in *def*.
  .. versionadded:: 3.5
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpythonmain\Doc\c-api\[cpython-main][Doc][c-api]module.rst, line 417)

Unknown directive type "c:function".

```
.. c:function:: int PyModule_SetDocString(PyObject *module, const char *docstring)
  Set the docstring for *module* to *docstring*.
  This function is called automatically when creating a module from
    `PyModuleDef``, using either ``PyModule Create`` or
  ``PyModule_FromDefAndSpec``.
  .. versionadded:: 3.5
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpythonmain\Doc\c-api\[cpython-main][Doc][c-api]module.rst, line 426)

Unknown directive type "c:function".

Py DECREF(obj); return res;

```
.. c:function:: int PyModule AddFunctions(PyObject *module, PyMethodDef *functions)
   Add the functions from the ``NULL`` terminated *functions* array to *module*.
   Refer to the :c:type:`PyMethodDef` documentation for details on individual
   entries (due to the lack of a shared module namespace, module level
   "functions" implemented in C typically receive the module as their first
   parameter, making them similar to instance methods on Python classes).
  This function is called automatically when creating a module from ``PyModuleDef``, using either ``PyModule_Create`` or
   ``PyModule_FromDefAndSpec``.
   .. versionadded:: 3.5
```

Support functions

The module initialization function (if using single phase initialization) or a function called from a module execution slot (if using multiphase initialization), can use the following functions to help initialize the module state:

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-
main\Doc\c-api\[cpython-main][Doc][c-api]module.rst, line 447)
Unknown directive type "c:function".
   .. c:function:: int PyModule_AddObjectRef(PyObject *module, const char *name, PyObject *value)
      Add an object to *module* as *name*. This is a convenience function which
      can be used from the module's initialization function.
      On success, return ``0``. On error, raise an exception and return ``-1``.
      Return ``NULL`` if *value* is ``NULL``. It must be called with an exception
      raised in this case.
      Example usage::
          static int
          add spam(PyObject *module, int value)
              PyObject *obj = PyLong_FromLong(value);
              if (obj == NULL) {
                  return -1;
              int res = PyModule_AddObjectRef(module, "spam", obj);
```

```
The example can also be written without checking explicitly if *obj* is
 `NULL``:
    static int
    add spam(PyObject *module, int value)
        PyObject *obj = PyLong_FromLong(value);
        int res = PyModule_AddObjectRef(module, "spam", obj);
        Py XDECREF (obj);
        return res;
Note that ``Py_XDECREF()`` should be used instead of ``Py_DECREF()`` in
this case, since *obj* can be ``NULL``.
.. versionadded:: 3.10
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpythonmain\Doc\c-api\[cpython-main][Doc][c-api]module.rst, line 489)

```
Unknown directive type "c:function".
   .. c:function:: int PyModule_AddObject(PyObject *module, const char *name, PyObject *velue)
      Similar to :c:func:`PyModule_AddObjectRef`, but steals a reference to
      *value* on success (if it returns ``0``).
      The new :c:func:`PyModule AddObjectRef` function is recommended, since it is
      easy to introduce reference leaks by misusing the
:c:func:`PyModule_AddObject` function.
      .. note::
         Unlike other functions that steal references, ``PyModule_AddObject()``
         only decrements the reference count of *value* **on success**.
         This means that its return value must be checked, and calling code must
         :c:func:`Py_DECREF` *value* manually on error.
      Example usage::
         static int
         add spam(PyObject *module, int value)
             PyObject *obj = PyLong_FromLong(value);
             if (obj == NULL) {
                  return -1;
             if (PyModule_AddObject(module, "spam", obj) < 0) {</pre>
                 Py DECREF(obj);
                 return -1;
              // PyModule_AddObject() stole a reference to obj:
             // Py DECREF(obj) is not needed here
             return 0:
      The example can also be written without checking explicitly if \text{*obj*} is
       `NULL``::
         static int
         add_spam(PyObject *module, int value)
             PyObject *obj = PyLong_FromLong(value);
             if (PyModule AddObject(module, "spam", obj) < 0) {
                 Py_XDECREF(obj);
                 return -1;
              // PyModule AddObject() stole a reference to obj:
              // Py_DECREF(obj) is not needed here
             return 0;
      Note that ``Py_XDECREF()`` should be used instead of ``Py_DECREF()`` in
      this case, since *obj* can be ``NULL``.
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpythonmain\Doc\c-api\[cpython-main][Doc][c-api]module.rst, line 544)

Unknown directive type "c:function".

```
.. c:function:: int PyModule_AddIntConstant(PyObject *module, const char *name, long value)
```

Add an integer constant to *module* as *name*. This convenience function can be used from the module's initialization function. Return ``-1`` on error, ``0`` on success.

 $System\,Message:\,ERROR/3\, (\mbox{D:\nonline}) \label{lem:control} $$ \end{System} Message:\,ERROR/3\, (\mbox{D:\nonline}) \end{System} $$ \end{$

Unknown directive type "c:function".

.. c:function:: int PyModule_AddStringConstant(PyObject *module, const char *name, const char *value)

Add a string constant to *module* as *name*. This convenience function can be used from the module's initialization function. The string *value* must be ``NULL``-terminated. Return ``-1`` on error, ``0`` on success.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] module.rst, line 558)

Unknown directive type "c:function".

.. c:function:: int PyModule_AddIntMacro(PyObject *module, macro)

Add an int constant to *module*. The name and the value are taken from *macro*. For example ``PyModule_AddIntMacro(module, AF_INET)`` adds the int constant *AF_INET* with the value of *AF_INET* to *module*. Return ``-1`` on error, ``0`` on success.

 $System\,Message:\,ERROR/3\, (\mboarding-resources\sample-onboarding-resources\cpython-main\clustering-resources) ample-onboarding-resources\cpython-main\clustering-resources. In 66 (b) and 66 (c) a$

Unknown directive type "c:function".

.. c:function:: int PyModule_AddStringMacro(PyObject *module, macro)

Add a string constant to *module*.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[continue] [continue] [continue]

Unknown directive type "c:function".

```
.. c:function:: int PyModule_AddType(PyObject *module, PyTypeObject *type)

Add a type object to *module*.

The type object is finalized by calling internally :c:func:`PyType_Ready`.

The name of the type object is taken from the last component of :c:member:`~PyTypeObject.tp_name` after dot.

Return ``-1`` on error, ``O`` on success.

.. versionadded:: 3.9
```

Module lookup

Single-phase initialization creates singleton modules that can be looked up in the context of the current interpreter. This allows the module object to be retrieved later with only a reference to the module definition.

These functions will not work on modules created using multi-phase initialization, since multiple such modules can be created from a single definition.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[cpython-main] [Doc] [c-api] module.rst, line 591)

Unknown directive type "c:function".

.. c:function:: PyObject* PyState_FindModule(PyModuleDef *def)

Returns the module object that was created from *def* for the current interpreter. This method requires that the module object has been attached to the interpreter state with :c:func:`PyState_AddModule` beforehand. In case the corresponding module object is not found or has not been attached to the interpreter state yet, it returns ``NULL``.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[continue] [Doc] [c-api]module.rst, line 598)

Unknown directive type "c:function".

.. c:function:: int PyState AddModule(PyObject *module, PyModuleDef *def)

Attaches the module object passed to the function to the interpreter state. This allows the module object to be accessible via :c:func:`PyState_FindModule`.

Only effective on modules created using single-phase initialization.

Python calls ``PyState_AddModule`` automatically after importing a module, so it is unnecessary (but harmless) to call it from module initialization code. An explicit call is needed only if the module's own init code subsequently calls ``PyState_FindModule``.

The function is mainly intended for implementing alternative import

The function is mainly intended for implementing alternative import mechanisms (either by calling it directly, or by referring to its implementation for details of the required state updates).

The caller must hold the GIL.

Return 0 on success or -1 on failure.

.. versionadded:: 3.3

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\c-api\[continue] [Doc] [c-api] module.rst, line 619)

Unknown directive type "c:function".

.. c:function:: int PyState RemoveModule(PyModuleDef *def)

Removes the module object created from *def* from the interpreter state. Return 0 on success or -1 on failure.

The caller must hold the GIL.

.. versionadded:: 3.3