Controlling how Ansible behaves: precedence rules

To give you maximum flexibility in managing your environments, Ansible offers many ways to control how Ansible behaves: how it connects to managed nodes, how it works once it has connected. If you use Ansible to manage a large number of servers, network devices, and cloud resources, you may define Ansible behavior in several different places and pass that information to Ansible in several different ways. This flexibility is convenient, but it can backfire if you do not understand the precedence rules.

These precedence rules apply to any setting that can be defined in multiple ways (by configuration settings, command-line options, playbook keywords, variables).

- Precedence categories
 - Configuration settings
 - Command-line options
 - Playbook keywords
 - Variables
 - Variable scope: how long is a value available?
 - Using -e extra variables at the command line

Precedence categories

Ansible offers four sources for controlling its behavior. In order of precedence from lowest (most easily overridden) to highest (overrides all others), the categories are:

- Configuration settings
- Command-line options
- Playbook keywords
- Variables

Each category overrides any information from all lower-precedence categories. For example, a playbook keyword will override any configuration setting.

Within each precedence category, specific rules apply. However, generally speaking, 'last defined' wins and overrides any previous definitions.

Configuration settings

ref. Configuration settings <ansible_configuration_settings >> include both values from the ansible.cfg file and environment variables. Within this category, values set in configuration files have lower precedence. Ansible uses the first ansible.cfg file it finds, ignoring all others. Ansible searches for ansible.cfg in these locations in order:

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\ansible-devel\docs\docsite\rst\reference_appendices\[ansible-devel] [docs] [docsite] [rst] [reference appendices] general precedence.rst, line 32); backlink

Unknown interpreted text role 'ref'.

- ANSIBLE_CONFIG (environment variable if set)
- ansible.cfg (in the current directory)
- ~/.ansible.cfg (in the home directory)
- /etc/ansible/ansible.cfg

Environment variables have a higher precedence than entries in ansible.cfg. If you have environment variables set on your control node, they override the settings in whichever ansible.cfg file Ansible loads. The value of any given environment variable follows normal shell precedence: the last value defined overwrites previous values.

Command-line options

Any command-line option will override any configuration setting.

When you type something directly at the command line, you may feel that your hand-crafted values should override all others, but Ansible does not work that way. Command-line options have low precedence - they override configuration only. They do not override playbook keywords, variables from inventory or variables from playbooks.

You can override all other settings from all other sources in all other precedence categories at the command line by ref. general_precedence_extra_vars', but that is not a command-line option, it is a way of passing a ref. variable general_precedence_variables>'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\ansible-devel\docs\docsite\rst\reference_appendices\[ansible-devel] [docs] [docsite] [rst] [reference appendices] general precedence.rst, line 48); backlink

Unknown interpreted text role 'ref'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\ansible-devel\docs\docsite\rst\reference_appendices\[ansible-devel] [docs] [docsite] [rst] [reference_appendices] general_precedence.rst, line 48); backlink

Unknown interpreted text role 'ref'.

At the command line, if you pass multiple values for a parameter that accepts only a single value, the last defined value wins. For example, this ref ad hoc task intro adhoc will connect as carol, not as mike:

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\ansible-devel\docs\docsite\rst\reference_appendices\[ansible-devel] [docs] [docsite] [rst] [reference_appendices] general_precedence.rst, line 50); backlink
Unknown interpreted text role "ref".
```

```
ansible -u mike -m ping myhost -u carol
```

Some parameters allow multiple values. In this case, Ansible will append all values from the hosts listed in inventory files inventory1 and inventory2:

```
ansible -i /path/inventory1 -i /path/inventory2 -m ping all
```

The help for each ref. command-line tool command line tools lists available options for that tool.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\ansible-devel\docs\docsite\rst\reference_appendices\[ansible-devel][docs][docsite][rst] [reference_appendices]general_precedence.rst, line 58); backlink
```

Unknown interpreted text role 'ref'.

Playbook keywords

Any ref: playbook keyword<playbook keywords> will override any command-line option and any configuration setting.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\ansible-devel\docs\docsite\rst\reference_appendices\[ansible-devel][docs][docsite][rst][reference_appendices]general_precedence.rst, line 63); backlink
Unknown interpreted text role "ref".
```

Within playbook keywords, precedence flows with the playbook itself, the more specific wins against the more general:

- play (most general)
- blocks/includes/imports/roles (optional and can contain tasks and each other)
- tasks (most specific)

A simple example:

```
    hosts: all
    connection: ssh
    tasks:

            name: This task uses ssh.
                ping:

    name: This task uses paramiko.
                connection: paramiko
                ping:
```

In this example, the connection keyword is set to ssh at the play level. The first task inherits that value, and connects using ssh. The second task inherits that value, overrides it, and connects using paramiko. The same logic applies to blocks and roles as well. All tasks, blocks, and roles within a play inherit play-level keywords; any task, block, or role can override any keyword by defining a different value for that keyword within the task, block, or role.

Remember that these are KEYWORDS, not variables. Both playbooks and variable files are defined in YAML but they have different significance. Playbooks are the command or 'state description' structure for Ansible, variables are data we use to help make

playbooks more dynamic.

Variables

Any variable will override any playbook keyword, any command-line option, and any configuration setting.

Variables that have equivalent playbook keywords, command-line options, and configuration settings are known as ref" connection_variables. Originally designed for connection parameters, this category has expanded to include other core variables like the temporary directory and the python interpreter.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\ansible-devel\docs\docsite\rst\reference_appendices\[ansible-devel] [docs] [docsite] [rst] [reference_appendices] general_precedence.rst, line 96); backlink
Unknown interpreted text role "ref".
```

Connection variables, like all variables, can be set in multiple ways and places. You can define variables for hosts and groups in ref. inventory intro_inventory. You can define variables for tasks and plays in vars: blocks in ref. playbooks about_playbooks. However, they are still variables - they are data, not keywords or configuration settings. Variables that override playbook keywords, command-line options, and configuration settings follow the same rules of ref. variable precedence variable variable precedence <a href="mailto

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\ansible-devel\docs\docsite\rst\reference_appendices\[ansible-devel] [docs] [docsite] [rst] [reference_appendices] general_precedence.rst, line 98); backlink
Unknown interpreted text role "ref".
```

```
System \, Message: ERROR/3 \, (\cite{Message: properties of the pr
```

Unknown interpreted text role "ref".

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\ansible-devel\docs\docsite\rst\reference_appendices\[ansible-devel] [docs] [docsite] [rst] [reference_appendices] general_precedence.rst, line 98); backlink
Unknown interpreted text role "ref".
```

When set in a playbook, variables follow the same inheritance rules as playbook keywords. You can set a value for the play, then override it in a task, block, or role:

```
- hosts: cloud
 gather facts: false
 become: yes
 vars:
   ansible_become_user: admin
   - name: This task uses admin as the become user.
       name: some-service
       state: latest
   - block:
       - name: This task uses service-admin as the become user.
          # a task to configure the new service
        - name: This task also uses service-admin as the become user, defined in the block.
          # second task to configure the service
     vars:
       ansible become user: service-admin
    - name: This task (outside of the block) uses admin as the become user again.
     service:
       name: some-service
       state: restarted
```

Variable scope: how long is a value available?

Variable values set in a playbook exist only within the playbook object that defines them. These 'playbook object scope' variables are not available to subsequent objects, including other plays.

Variable values associated directly with a host or group, including variables defined in inventory, by vars plugins, or using modules like ref include vars include vars include vars module>`, are available to all plays. These 'host scope'

variables are also available via the hostvars[] dictionary.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\ansible-devel\docs\docsite\rst\reference_appendices\[ansible-devel] [docs] [docsite] [rst] [reference_appendices] general_precedence.rst, line 129); backlink

Unknown interpreted text role 'ref'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\ansible-devel\docs\docsite\rst\reference_appendices\[ansible-devel] [docs] [docsite] [rst] [reference_appendices] general_precedence.rst, line 129); backlink

Unknown interpreted text role 'ref'.

Using -e extra variables at the command line

To override all other settings in all other categories, you can use extra variables: --extra-vars or -e at the command line. Values passed with -e are variables, not command-line options, and they will override configuration settings, command-line options, and playbook keywords as well as variables set elsewhere. For example, this task will connect as brian not as carol:

```
ansible -u carol -e 'ansible_user=brian' -a whoami all
```

You must specify both the variable name and the value with --extra-vars.